

Free Pascal Resource support (FCL-res):  
Reference guide.

---

Reference guide for FCL-res units.  
Document version 3.0.4  
March 2019

Giulio Bernardi

---

# Contents

0.1	Introduction . . . . .	20
0.2	Basic Usage . . . . .	20
0.3	How to implement a new resource class . . . . .	26
0.4	How to implement a new resource reader . . . . .	30
0.5	How to implement a new resource writer . . . . .	36
0.6	Format of resources in object files . . . . .	39
<b>1</b>	<b>Reference for unit 'acceleratorsresource'</b>	<b>42</b>
1.1	Used units . . . . .	42
1.2	Overview . . . . .	42
1.3	Constants, types and variables . . . . .	42
1.3.1	Constants . . . . .	42
1.3.2	Types . . . . .	43
1.4	TAcceleratorsResource . . . . .	43
1.4.1	Description . . . . .	43
1.4.2	Method overview . . . . .	44
1.4.3	Property overview . . . . .	44
1.4.4	TAcceleratorsResource.GetType . . . . .	44
1.4.5	TAcceleratorsResource.GetName . . . . .	44
1.4.6	TAcceleratorsResource.ChangeDescTypeAllowed . . . . .	44
1.4.7	TAcceleratorsResource.ChangeDescValueAllowed . . . . .	44
1.4.8	TAcceleratorsResource.NotifyResourcesLoaded . . . . .	44
1.4.9	TAcceleratorsResource.Create . . . . .	45
1.4.10	TAcceleratorsResource.Destroy . . . . .	45
1.4.11	TAcceleratorsResource.UpdateRawData . . . . .	45
1.4.12	TAcceleratorsResource.Add . . . . .	45
1.4.13	TAcceleratorsResource.Clear . . . . .	45
1.4.14	TAcceleratorsResource.Delete . . . . .	45
1.4.15	TAcceleratorsResource.Count . . . . .	46
1.4.16	TAcceleratorsResource.Items . . . . .	46
<b>2</b>	<b>Reference for unit 'bitmapresource'</b>	<b>47</b>

2.1	Used units	47
2.2	Overview	47
2.3	TBitmapResource	47
2.3.1	Description	47
2.3.2	Method overview	48
2.3.3	Property overview	48
2.3.4	TBitmapResource.GetType	48
2.3.5	TBitmapResource.GetName	48
2.3.6	TBitmapResource.ChangeDescTypeAllowed	48
2.3.7	TBitmapResource.ChangeDescValueAllowed	48
2.3.8	TBitmapResource.NotifyResourcesLoaded	48
2.3.9	TBitmapResource.Create	49
2.3.10	TBitmapResource.Destroy	49
2.3.11	TBitmapResource.UpdateRawData	49
2.3.12	TBitmapResource.SetCustomBitmapDataStream	49
2.3.13	TBitmapResource.BitmapData	50
<b>3</b>	<b>Reference for unit 'coffreader'</b>	<b>51</b>
3.1	Used units	51
3.2	Overview	51
3.3	TCoffResourceReader	51
3.3.1	Description	51
3.3.2	Method overview	52
3.3.3	Property overview	52
3.3.4	TCoffResourceReader.GetExtensions	52
3.3.5	TCoffResourceReader.GetDescription	52
3.3.6	TCoffResourceReader.Load	52
3.3.7	TCoffResourceReader.CheckMagic	52
3.3.8	TCoffResourceReader.Create	52
3.3.9	TCoffResourceReader.Destroy	52
3.3.10	TCoffResourceReader.MachineType	53
<b>4</b>	<b>Reference for unit 'cofftypes'</b>	<b>54</b>
4.1	Used units	54
4.2	Overview	54
4.3	Constants, types and variables	54
4.3.1	Constants	54
4.3.2	Types	54
<b>5</b>	<b>Reference for unit 'coffwriter'</b>	<b>58</b>
5.1	Used units	58

---

5.2	Overview	58
5.3	Constants, types and variables	58
5.3.1	Types	58
5.4	TCoffRelocations	59
5.4.1	Description	59
5.4.2	Method overview	59
5.4.3	Property overview	59
5.4.4	TCoffRelocations.GetCount	59
5.4.5	TCoffRelocations.GetRelocation	59
5.4.6	TCoffRelocations.Create	59
5.4.7	TCoffRelocations.Destroy	59
5.4.8	TCoffRelocations.Add	60
5.4.9	TCoffRelocations.AddRelativeToSection	60
5.4.10	TCoffRelocations.Clear	60
5.4.11	TCoffRelocations.Count	60
5.4.12	TCoffRelocations.Items	60
5.4.13	TCoffRelocations.StartAddress	60
5.4.14	TCoffRelocations.MachineType	60
5.5	TCoffResourceWriter	61
5.5.1	Description	61
5.5.2	Method overview	61
5.5.3	Property overview	61
5.5.4	TCoffResourceWriter.WriteEmptyCoffHeader	61
5.5.5	TCoffResourceWriter.WriteEmptySectionHeader	61
5.5.6	TCoffResourceWriter.WriteResStringTable	62
5.5.7	TCoffResourceWriter.WriteRawData	62
5.5.8	TCoffResourceWriter.WriteRelocations	62
5.5.9	TCoffResourceWriter.WriteCoffStringTable	62
5.5.10	TCoffResourceWriter.GetFixedCoffHeader	62
5.5.11	TCoffResourceWriter.FixCoffHeader	62
5.5.12	TCoffResourceWriter.FixSectionHeader	62
5.5.13	TCoffResourceWriter.GetExtensions	62
5.5.14	TCoffResourceWriter.GetDescription	62
5.5.15	TCoffResourceWriter.PrescanNode	63
5.5.16	TCoffResourceWriter.PrescanResourceTree	63
5.5.17	TCoffResourceWriter.Write	63
5.5.18	TCoffResourceWriter.WriteSymbolTable	63
5.5.19	TCoffResourceWriter.Create	63
5.5.20	TCoffResourceWriter.Destroy	63
5.5.21	TCoffResourceWriter.MachineType	63

5.5.22	T CoffResourceWriter.OppositeEndianness	64
5.6	T CoffStringTable	64
5.6.1	Method overview	64
5.6.2	Property overview	64
5.6.3	T CoffStringTable.Create	64
5.6.4	T CoffStringTable.Add	64
5.6.5	T CoffStringTable.Delete	64
5.6.6	T CoffStringTable.Size	64
5.7	T ResourceStringTable	64
5.7.1	Description	64
5.7.2	Method overview	65
5.7.3	Property overview	65
5.7.4	T ResourceStringTable.Create	65
5.7.5	T ResourceStringTable.Destroy	65
5.7.6	T ResourceStringTable.Add	65
5.7.7	T ResourceStringTable.Clear	65
5.7.8	T ResourceStringTable.Count	65
5.7.9	T ResourceStringTable.Items	66
5.7.10	T ResourceStringTable.StartRVA	66
5.7.11	T ResourceStringTable.CurrRVA	66
5.7.12	T ResourceStringTable.EndRVA	66
<b>6</b>	<b>Reference for unit 'dfmreader'</b>	<b>67</b>
6.1	Used units	67
6.2	Overview	67
6.3	TDfmResourceReader	67
6.3.1	Description	67
6.3.2	Method overview	68
6.3.3	TDfmResourceReader.GetExtensions	68
6.3.4	TDfmResourceReader.GetDescription	68
6.3.5	TDfmResourceReader.Load	68
6.3.6	TDfmResourceReader.CheckMagic	68
6.3.7	TDfmResourceReader.Create	68
6.3.8	TDfmResourceReader.Destroy	68
<b>7</b>	<b>Reference for unit 'elfconsts'</b>	<b>69</b>
7.1	Used units	69
7.2	Overview	69
7.3	Constants, types and variables	69
7.3.1	Constants	69
7.3.2	Types	74

<b>8</b>	<b>Reference for unit 'elfreader'</b>	<b>75</b>
8.1	Used units	75
8.2	Overview	75
8.3	EElfResourceReaderException	75
8.3.1	Description	75
8.4	EElfResourceReaderNoSectionsException	75
8.4.1	Description	75
8.5	EElfResourceReaderNoStringTableException	76
8.5.1	Description	76
8.6	EElfResourceReaderUnknownClassException	76
8.6.1	Description	76
8.7	EElfResourceReaderUnknownVersionException	76
8.7.1	Description	76
8.8	TElfResourceReader	76
8.8.1	Description	76
8.8.2	Method overview	76
8.8.3	Property overview	77
8.8.4	TElfResourceReader.GetExtensions	77
8.8.5	TElfResourceReader.GetDescription	77
8.8.6	TElfResourceReader.Load	77
8.8.7	TElfResourceReader.CheckMagic	77
8.8.8	TElfResourceReader.Create	77
8.8.9	TElfResourceReader.Destroy	77
8.8.10	TElfResourceReader.MachineType	77
<b>9</b>	<b>Reference for unit 'elfwriter'</b>	<b>78</b>
9.1	Used units	78
9.2	Overview	78
9.3	EElfResourceWriterException	78
9.3.1	Description	78
9.4	EElfResourceWriterUnknownClassException	78
9.4.1	Description	78
9.5	EElfResourceWriterUnknownMachineException	79
9.5.1	Description	79
9.6	EElfResourceWriterUnknownSectionException	79
9.6.1	Description	79
9.7	TElfResourceWriter	79
9.7.1	Description	79
9.7.2	Method overview	79
9.7.3	Property overview	79

9.7.4	TElfResourceWriter.GetExtensions	79
9.7.5	TElfResourceWriter.GetDescription	80
9.7.6	TElfResourceWriter.Write	80
9.7.7	TElfResourceWriter.Create	80
9.7.8	TElfResourceWriter.Destroy	80
9.7.9	TElfResourceWriter.MachineType	80
<b>10</b>	<b>Reference for unit 'externalreader'</b>	<b>81</b>
10.1	Used units	81
10.2	Overview	81
10.3	TExternalResourceReader	81
10.3.1	Description	81
10.3.2	Method overview	82
10.3.3	Property overview	82
10.3.4	TExternalResourceReader.GetExtensions	82
10.3.5	TExternalResourceReader.GetDescription	82
10.3.6	TExternalResourceReader.Load	82
10.3.7	TExternalResourceReader.CheckMagic	82
10.3.8	TExternalResourceReader.Create	82
10.3.9	TExternalResourceReader.Destroy	82
10.3.10	TExternalResourceReader.Endianess	83
<b>11</b>	<b>Reference for unit 'externaltypes'</b>	<b>84</b>
11.1	Used units	84
11.2	Overview	84
11.3	Description of external resource file format	84
11.4	Constants, types and variables	87
11.4.1	Constants	87
11.4.2	Types	87
<b>12</b>	<b>Reference for unit 'externalwriter'</b>	<b>88</b>
12.1	Used units	88
12.2	Overview	88
12.3	EExternalResInvalidEndianessException	88
12.3.1	Description	88
12.4	EExternalResourceWriterException	89
12.4.1	Description	89
12.5	TExternalResourceWriter	89
12.5.1	Description	89
12.5.2	Method overview	89
12.5.3	Property overview	89

12.5.4	TExternalResourceWriter.GetExtensions	89
12.5.5	TExternalResourceWriter.GetDescription	89
12.5.6	TExternalResourceWriter.Write	89
12.5.7	TExternalResourceWriter.Create	90
12.5.8	TExternalResourceWriter.Destroy	90
12.5.9	TExternalResourceWriter.Endianess	90
<b>13</b>	<b>Reference for unit 'groupcursorresource'</b>	<b>91</b>
13.1	Used units	91
13.2	Overview	91
13.3	TGroupCursorResource	91
13.3.1	Description	91
13.3.2	Method overview	92
13.3.3	TGroupCursorResource.ReadResourceItemHeader	92
13.3.4	TGroupCursorResource.WriteHeader	92
13.3.5	TGroupCursorResource.CreateSubItem	92
13.3.6	TGroupCursorResource.UpdateItemOwner	92
13.3.7	TGroupCursorResource.ClearItemList	93
13.3.8	TGroupCursorResource.DeleteSubItems	93
13.3.9	TGroupCursorResource.GetSubStream	93
13.3.10	TGroupCursorResource.GetType	93
13.3.11	TGroupCursorResource.GetName	93
13.3.12	TGroupCursorResource.ChangeDescTypeAllowed	93
13.3.13	TGroupCursorResource.ChangeDescValueAllowed	93
13.3.14	TGroupCursorResource.Create	93
<b>14</b>	<b>Reference for unit 'groupiconresource'</b>	<b>95</b>
14.1	Used units	95
14.2	Overview	95
14.3	TGroupIconResource	95
14.3.1	Description	95
14.3.2	Method overview	96
14.3.3	TGroupIconResource.ReadResourceItemHeader	96
14.3.4	TGroupIconResource.WriteHeader	96
14.3.5	TGroupIconResource.CreateSubItem	96
14.3.6	TGroupIconResource.UpdateItemOwner	96
14.3.7	TGroupIconResource.ClearItemList	97
14.3.8	TGroupIconResource.DeleteSubItems	97
14.3.9	TGroupIconResource.GetSubStream	97
14.3.10	TGroupIconResource.GetType	97
14.3.11	TGroupIconResource.GetName	97



14.3.12 TGroupIconResource.ChangeDescTypeAllowed . . . . .	97
14.3.13 TGroupIconResource.ChangeDescValueAllowed . . . . .	97
14.3.14 TGroupIconResource.Create . . . . .	97
<b>15 Reference for unit 'groupresource'</b>	<b>99</b>
15.1 Used units . . . . .	99
15.2 Overview . . . . .	99
15.3 TGroupCachedDataStream . . . . .	99
15.3.1 Description . . . . .	99
15.3.2 Method overview . . . . .	100
15.3.3 TGroupCachedDataStream.Create . . . . .	100
15.3.4 TGroupCachedDataStream.Destroy . . . . .	100
15.3.5 TGroupCachedDataStream.Read . . . . .	100
15.4 TGroupResource . . . . .	100
15.4.1 Description . . . . .	100
15.4.2 Method overview . . . . .	101
15.4.3 Property overview . . . . .	101
15.4.4 TGroupResource.FindSubResources . . . . .	101
15.4.5 TGroupResource.ReadResourceItemHeader . . . . .	101
15.4.6 TGroupResource.CheckBuildItemStream . . . . .	101
15.4.7 TGroupResource.GetItemData . . . . .	101
15.4.8 TGroupResource.WriteHeader . . . . .	102
15.4.9 TGroupResource.WriteResHeader . . . . .	102
15.4.10 TGroupResource.CreateSubItems . . . . .	102
15.4.11 TGroupResource.CreateSubItem . . . . .	102
15.4.12 TGroupResource.UpdateItemOwner . . . . .	102
15.4.13 TGroupResource.ClearItemList . . . . .	102
15.4.14 TGroupResource.DeleteSubItems . . . . .	102
15.4.15 TGroupResource.GetSubStreamCount . . . . .	102
15.4.16 TGroupResource.GetSubStream . . . . .	102
15.4.17 TGroupResource.SetOwnerList . . . . .	103
15.4.18 TGroupResource.NotifyResourcesLoaded . . . . .	103
15.4.19 TGroupResource.Destroy . . . . .	103
15.4.20 TGroupResource.CompareContents . . . . .	103
15.4.21 TGroupResource.SetCustomItemDataStream . . . . .	103
15.4.22 TGroupResource.UpdateRawData . . . . .	104
15.4.23 TGroupResource.ItemData . . . . .	104
<b>16 Reference for unit 'machoreader'</b>	<b>105</b>
16.1 Used units . . . . .	105
16.2 Overview . . . . .	105

16.3	TMachOResourceReader	105
16.3.1	Description	105
16.3.2	Method overview	106
16.3.3	Property overview	106
16.3.4	TMachOResourceReader.GetExtensions	106
16.3.5	TMachOResourceReader.GetDescription	106
16.3.6	TMachOResourceReader.Load	106
16.3.7	TMachOResourceReader.CheckMagic	106
16.3.8	TMachOResourceReader.Create	106
16.3.9	TMachOResourceReader.Destroy	106
16.3.10	TMachOResourceReader.MachineType	107
<b>17</b>	<b>Reference for unit 'machotypes'</b>	<b>108</b>
17.1	Used units	108
17.2	Overview	108
17.3	Constants, types and variables	108
17.3.1	Types	108
<b>18</b>	<b>Reference for unit 'machowriter'</b>	<b>113</b>
18.1	Used units	113
18.2	Overview	113
18.3	Constants, types and variables	113
18.3.1	Types	113
18.4	EMachOResourceWriterException	114
18.4.1	Description	114
18.5	EMachOResourceWriterUnknownBitSizeException	114
18.5.1	Description	114
18.6	TMachOResourceWriter	114
18.6.1	Description	114
18.6.2	Method overview	114
18.6.3	Property overview	115
18.6.4	TMachOResourceWriter.GetExtensions	115
18.6.5	TMachOResourceWriter.GetDescription	115
18.6.6	TMachOResourceWriter.Write	115
18.6.7	TMachOResourceWriter.Create	115
18.6.8	TMachOResourceWriter.Destroy	115
18.6.9	TMachOResourceWriter.MachineType	115
18.6.10	TMachOResourceWriter.SubMachineType	116
<b>19</b>	<b>Reference for unit 'resdatastream'</b>	<b>117</b>
19.1	Used units	117

19.2 Overview	117
19.3 Constants, types and variables	117
19.3.1 Types	117
19.4 TCachedDataStream	118
19.4.1 Description	118
19.4.2 Method overview	118
19.4.3 TCachedDataStream.GetPosition	118
19.4.4 TCachedDataStream.SetPosition	118
19.4.5 TCachedDataStream.GetSize	119
19.4.6 TCachedDataStream.SetSize64	119
19.4.7 TCachedDataStream.Create	119
19.4.8 TCachedDataStream.Write	119
19.4.9 TCachedDataStream.Seek	119
19.5 TCachedResourceDataStream	119
19.5.1 Description	119
19.5.2 Method overview	119
19.5.3 TCachedResourceDataStream.Create	120
19.5.4 TCachedResourceDataStream.Read	120
19.6 TResourceDataStream	120
19.6.1 Description	120
19.6.2 Method overview	121
19.6.3 Property overview	121
19.6.4 TResourceDataStream.GetPosition	121
19.6.5 TResourceDataStream.SetPosition	121
19.6.6 TResourceDataStream.GetSize	121
19.6.7 TResourceDataStream.SetSize64	121
19.6.8 TResourceDataStream.Create	121
19.6.9 TResourceDataStream.Destroy	122
19.6.10 TResourceDataStream.Compare	122
19.6.11 TResourceDataStream.SetCustomStream	122
19.6.12 TResourceDataStream.Read	122
19.6.13 TResourceDataStream.Write	122
19.6.14 TResourceDataStream.Seek	123
19.6.15 TResourceDataStream.Cached	123
<b>20 Reference for unit 'resfactory'</b>	<b>124</b>
20.1 Used units	124
20.2 Overview	124
20.3 Constants, types and variables	124
20.3.1 Resource strings	124

20.4	<a href="#">EResourceClassAlreadyRegisteredException</a>	124
20.4.1	<a href="#">Description</a>	124
20.5	<a href="#">EResourceFactoryException</a>	125
20.5.1	<a href="#">Description</a>	125
20.6	<a href="#">TResourceFactory</a>	125
20.6.1	<a href="#">Description</a>	125
20.6.2	<a href="#">Method overview</a>	125
20.6.3	<a href="#">TResourceFactory.RegisterResourceClass</a>	125
20.6.4	<a href="#">TResourceFactory.CreateResource</a>	125
<b>21</b>	<b>Reference for unit 'resource'</b>	<b>127</b>
21.1	<a href="#">Used units</a>	127
21.2	<a href="#">Overview</a>	127
21.3	<a href="#">Constants, types and variables</a>	127
21.3.1	<a href="#">Resource strings</a>	127
21.3.2	<a href="#">Constants</a>	128
21.3.3	<a href="#">Types</a>	130
21.4	<a href="#">ENoMoreFreeIDsException</a>	131
21.4.1	<a href="#">Description</a>	131
21.5	<a href="#">EResourceDescChangeNotAllowedException</a>	131
21.5.1	<a href="#">Description</a>	131
21.6	<a href="#">EResourceDescTypeException</a>	131
21.6.1	<a href="#">Description</a>	131
21.7	<a href="#">EResourceDuplicateException</a>	132
21.7.1	<a href="#">Description</a>	132
21.8	<a href="#">EResourceException</a>	132
21.8.1	<a href="#">Description</a>	132
21.9	<a href="#">EResourceLangIDChangeNotAllowedException</a>	132
21.9.1	<a href="#">Description</a>	132
21.10	<a href="#">EResourceNotFoundException</a>	132
21.10.1	<a href="#">Description</a>	132
21.11	<a href="#">EResourceReaderException</a>	132
21.11.1	<a href="#">Description</a>	132
21.12	<a href="#">EResourceReaderNotFoundException</a>	132
21.12.1	<a href="#">Description</a>	132
21.13	<a href="#">EResourceReaderUnexpectedEndOfStreamException</a>	133
21.13.1	<a href="#">Description</a>	133
21.14	<a href="#">EResourceReaderWrongFormatException</a>	133
21.14.1	<a href="#">Description</a>	133
21.15	<a href="#">EResourceWriterException</a>	133

21.15.1 Description . . . . .	133
21.16EResourceWriterNotFoundException . . . . .	133
21.16.1 Description . . . . .	133
21.17TAbstractResource . . . . .	133
21.17.1 Description . . . . .	133
21.17.2 Method overview . . . . .	134
21.17.3 Property overview . . . . .	135
21.17.4 TAbstractResource.SetDescOwner . . . . .	135
21.17.5 TAbstractResource.SetOwnerList . . . . .	135
21.17.6 TAbstractResource.SetChildOwner . . . . .	135
21.17.7 TAbstractResource.GetType . . . . .	135
21.17.8 TAbstractResource.GetName . . . . .	136
21.17.9 TAbstractResource.ChangeDescTypeAllowed . . . . .	136
21.17.10TAbstractResource.ChangeDescValueAllowed . . . . .	136
21.17.11TAbstractResource.NotifyResourcesLoaded . . . . .	137
21.17.12TAbstractResource.Create . . . . .	137
21.17.13TAbstractResource.Destroy . . . . .	137
21.17.14TAbstractResource.CompareContents . . . . .	137
21.17.15TAbstractResource.UpdateRawData . . . . .	138
21.17.16TAbstractResource.SetCustomRawDataStream . . . . .	138
21.17.17TAbstractResource._Type . . . . .	139
21.17.18TAbstractResource.Name . . . . .	139
21.17.19TAbstractResource.LangID . . . . .	139
21.17.20TAbstractResource.DataSize . . . . .	139
21.17.21TAbstractResource.HeaderSize . . . . .	140
21.17.22TAbstractResource.DataVersion . . . . .	140
21.17.23TAbstractResource.MemoryFlags . . . . .	140
21.17.24TAbstractResource.Version . . . . .	141
21.17.25TAbstractResource.Characteristics . . . . .	141
21.17.26TAbstractResource.DataOffset . . . . .	141
21.17.27TAbstractResource.CodePage . . . . .	141
21.17.28TAbstractResource.RawData . . . . .	142
21.17.29TAbstractResource.CacheData . . . . .	142
21.17.30TAbstractResource.OwnerList . . . . .	142
21.17.31TAbstractResource.Owner . . . . .	143
21.18TAbstractResourceReader . . . . .	143
21.18.1 Description . . . . .	143
21.18.2 Method overview . . . . .	144
21.18.3 Property overview . . . . .	144
21.18.4 TAbstractResourceReader.SetDataSize . . . . .	144

21.18.5 TAbstractResourceReader.SetHeaderSize . . . . .	144
21.18.6 TAbstractResourceReader.SetDataOffset . . . . .	145
21.18.7 TAbstractResourceReader.SetRawData . . . . .	145
21.18.8 TAbstractResourceReader.CallSubReaderLoad . . . . .	145
21.18.9 TAbstractResourceReader.AddNoTree . . . . .	145
21.18.10 TAbstractResourceReader.GetTree . . . . .	146
21.18.11 TAbstractResourceReader.GetExtensions . . . . .	146
21.18.12 TAbstractResourceReader.GetDescription . . . . .	146
21.18.13 TAbstractResourceReader.Load . . . . .	146
21.18.14 TAbstractResourceReader.CheckMagic . . . . .	147
21.18.15 TAbstractResourceReader.Create . . . . .	147
21.18.16 TAbstractResourceReader.Extensions . . . . .	147
21.18.17 TAbstractResourceReader.Description . . . . .	148
21.19 TAbstractResourceWriter . . . . .	148
21.19.1 Description . . . . .	148
21.19.2 Method overview . . . . .	148
21.19.3 Property overview . . . . .	148
21.19.4 TAbstractResourceWriter.GetTree . . . . .	149
21.19.5 TAbstractResourceWriter.GetExtensions . . . . .	149
21.19.6 TAbstractResourceWriter.GetDescription . . . . .	149
21.19.7 TAbstractResourceWriter.Write . . . . .	149
21.19.8 TAbstractResourceWriter.Create . . . . .	150
21.19.9 TAbstractResourceWriter.Extensions . . . . .	150
21.19.10 TAbstractResourceWriter.Description . . . . .	150
21.20 TGenericResource . . . . .	150
21.20.1 Description . . . . .	150
21.20.2 Method overview . . . . .	151
21.20.3 TGenericResource.GetType . . . . .	151
21.20.4 TGenericResource.GetName . . . . .	151
21.20.5 TGenericResource.ChangeDescTypeAllowed . . . . .	151
21.20.6 TGenericResource.ChangeDescValueAllowed . . . . .	151
21.20.7 TGenericResource.NotifyResourcesLoaded . . . . .	151
21.20.8 TGenericResource.Create . . . . .	151
21.20.9 TGenericResource.Destroy . . . . .	152
21.20.10 TGenericResource.UpdateRawData . . . . .	152
21.21 TResourceDesc . . . . .	152
21.21.1 Description . . . . .	152
21.21.2 Method overview . . . . .	152
21.21.3 Property overview . . . . .	152
21.21.4 TResourceDesc.SetOwner . . . . .	152

21.21.5 TResourceDesc.Create	153
21.21.6 TResourceDesc.Assign	153
21.21.7 TResourceDesc.Equals	153
21.21.8 TResourceDesc.Name	153
21.21.9 TResourceDesc.ID	154
21.21.10 TResourceDesc.DescType	154
21.22 TResources	154
21.22.1 Description	154
21.22.2 Method overview	155
21.22.3 Property overview	155
21.22.4 TResources.Create	155
21.22.5 TResources.Destroy	155
21.22.6 TResources.Add	155
21.22.7 TResources.AddAutoID	156
21.22.8 TResources.Clear	156
21.22.9 TResources.Find	156
21.22.10 TResources.FindReader	157
21.22.11 TResources.MoveFrom	157
21.22.12 TResources.Remove	157
21.22.13 TResources.LoadFromStream	158
21.22.14 TResources.LoadFromFile	158
21.22.15 TResources.RegisterReader	159
21.22.16 TResources.RegisterWriter	159
21.22.17 TResources.WriteToStream	160
21.22.18 TResources.WriteToFile	160
21.22.19 TResources.Count	160
21.22.20 TResources.Items	161
21.22.21 TResources.CacheData	161
<b>22 Reference for unit 'resourcetree'</b>	<b>162</b>
22.1 Used units	162
22.2 Overview	162
22.3 TResourceTreeNode	163
22.3.1 Description	163
22.3.2 Method overview	163
22.3.3 Property overview	163
22.3.4 TResourceTreeNode.GetNamedCount	163
22.3.5 TResourceTreeNode.GetNamedEntry	163
22.3.6 TResourceTreeNode.GetIDCount	164
22.3.7 TResourceTreeNode.GetIDEntry	164

22.3.8	TResourceTreeNode.GetData	164
22.3.9	TResourceTreeNode.InternalFind	164
22.3.10	TResourceTreeNode.Create	164
22.3.11	TResourceTreeNode.Destroy	164
22.3.12	TResourceTreeNode.Add	164
22.3.13	TResourceTreeNode.CreateSubNode	165
22.3.14	TResourceTreeNode.CreateResource	165
22.3.15	TResourceTreeNode.Clear	165
22.3.16	TResourceTreeNode.Remove	165
22.3.17	TResourceTreeNode.Find	166
22.3.18	TResourceTreeNode.FindFreeID	166
22.3.19	TResourceTreeNode.IsLeaf	166
22.3.20	TResourceTreeNode.Parent	166
22.3.21	TResourceTreeNode.Desc	167
22.3.22	TResourceTreeNode.NamedCount	167
22.3.23	TResourceTreeNode.NamedEntries	167
22.3.24	TResourceTreeNode.IDCount	167
22.3.25	TResourceTreeNode.IDEntries	168
22.3.26	TResourceTreeNode.NameRVA	168
22.3.27	TResourceTreeNode.SubDirRVA	168
22.3.28	TResourceTreeNode.DataRVA	169
22.3.29	TResourceTreeNode.Data	169
22.4	TRootResTreeNode	169
22.4.1	Description	169
22.4.2	Method overview	169
22.4.3	TRootResTreeNode.InternalFind	170
22.4.4	TRootResTreeNode.Create	170
22.4.5	TRootResTreeNode.CreateSubNode	170
22.4.6	TRootResTreeNode.Add	170
22.4.7	TRootResTreeNode.FindFreeID	170
<b>23</b>	<b>Reference for unit 'resreader'</b>	<b>171</b>
23.1	Used units	171
23.2	Overview	171
23.3	TResResourceReader	171
23.3.1	Description	171
23.3.2	Method overview	172
23.3.3	TResResourceReader.GetExtensions	172
23.3.4	TResResourceReader.GetDescription	172
23.3.5	TResResourceReader.Load	172



23.3.6	<a href="#">TResResourceReader.CheckMagic</a>	172
23.3.7	<a href="#">TResResourceReader.Create</a>	172
23.3.8	<a href="#">TResResourceReader.Destroy</a>	172
<b>24</b>	<b>Reference for unit 'reswriter'</b>	<b>173</b>
24.1	Used units	173
24.2	Overview	173
24.3	<a href="#">TResResourceWriter</a>	173
24.3.1	Description	173
24.3.2	Method overview	174
24.3.3	<a href="#">TResResourceWriter.GetExtensions</a>	174
24.3.4	<a href="#">TResResourceWriter.GetDescription</a>	174
24.3.5	<a href="#">TResResourceWriter.Write</a>	174
24.3.6	<a href="#">TResResourceWriter.Create</a>	174
<b>25</b>	<b>Reference for unit 'stringtableresource'</b>	<b>175</b>
25.1	Used units	175
25.2	Overview	175
25.3	Constants, types and variables	175
25.3.1	Resource strings	175
25.4	<a href="#">EStringTableIndexOutOfBoundsException</a>	176
25.4.1	Description	176
25.5	<a href="#">EStringTableNameNotAllowedException</a>	176
25.5.1	Description	176
25.6	<a href="#">EStringTableResourceException</a>	176
25.6.1	Description	176
25.7	<a href="#">TStringTableResource</a>	176
25.7.1	Description	176
25.7.2	Method overview	177
25.7.3	Property overview	177
25.7.4	<a href="#">TStringTableResource.GetType</a>	177
25.7.5	<a href="#">TStringTableResource.GetName</a>	177
25.7.6	<a href="#">TStringTableResource.ChangeDescTypeAllowed</a>	177
25.7.7	<a href="#">TStringTableResource.ChangeDescValueAllowed</a>	177
25.7.8	<a href="#">TStringTableResource.NotifyResourcesLoaded</a>	177
25.7.9	<a href="#">TStringTableResource.Create</a>	178
25.7.10	<a href="#">TStringTableResource.Destroy</a>	178
25.7.11	<a href="#">TStringTableResource.UpdateRawData</a>	178
25.7.12	<a href="#">TStringTableResource.FirstID</a>	178
25.7.13	<a href="#">TStringTableResource.LastID</a>	179
25.7.14	<a href="#">TStringTableResource.Count</a>	179

25.7.15 TStringTableResource.Strings	179
<b>26 Reference for unit 'versionconsts'</b>	<b>180</b>
26.1 Used units	180
26.2 Overview	180
26.3 Constants, types and variables	182
26.3.1 Constants	182
<b>27 Reference for unit 'versionresource'</b>	<b>186</b>
27.1 Used units	186
27.2 Overview	186
27.3 Constants, types and variables	186
27.3.1 Types	186
27.4 TVersionResource	187
27.4.1 Description	187
27.4.2 Method overview	188
27.4.3 Property overview	188
27.4.4 TVersionResource.GetType	188
27.4.5 TVersionResource.GetName	188
27.4.6 TVersionResource.ChangeDescTypeAllowed	188
27.4.7 TVersionResource.ChangeDescValueAllowed	188
27.4.8 TVersionResource.NotifyResourcesLoaded	189
27.4.9 TVersionResource.Create	189
27.4.10 TVersionResource.Destroy	189
27.4.11 TVersionResource.UpdateRawData	189
27.4.12 TVersionResource.FixedInfo	189
27.4.13 TVersionResource.StringFileInfo	189
27.4.14 TVersionResource.VarFileInfo	190
<b>28 Reference for unit 'versiontypes'</b>	<b>191</b>
28.1 Used units	191
28.2 Overview	191
28.3 Constants, types and variables	191
28.3.1 Resource strings	191
28.3.2 Types	191
28.4 EDuplicateKeyException	192
28.4.1 Description	192
28.5 EKeyNotFoundException	192
28.5.1 Description	192
28.6 ENameNotAllowedException	192
28.6.1 Description	192

28.7	EVersionStringTableException	192
28.7.1	Description	192
28.8	TVersionFixedInfo	193
28.8.1	Description	193
28.8.2	Method overview	193
28.8.3	Property overview	193
28.8.4	TVersionFixedInfo.Create	193
28.8.5	TVersionFixedInfo.FileVersion	193
28.8.6	TVersionFixedInfo.ProductVersion	193
28.8.7	TVersionFixedInfo.FileFlagsMask	194
28.8.8	TVersionFixedInfo.FileFlags	194
28.8.9	TVersionFixedInfo.FileOS	194
28.8.10	TVersionFixedInfo.FileType	195
28.8.11	TVersionFixedInfo.FileSubType	195
28.8.12	TVersionFixedInfo.FileDate	196
28.9	TVersionStringFileInfo	196
28.9.1	Description	196
28.9.2	Method overview	196
28.9.3	Property overview	197
28.9.4	TVersionStringFileInfo.GetCount	197
28.9.5	TVersionStringFileInfo.GetItem	197
28.9.6	TVersionStringFileInfo.SetItem	197
28.9.7	TVersionStringFileInfo.Create	197
28.9.8	TVersionStringFileInfo.Destroy	197
28.9.9	TVersionStringFileInfo.Add	197
28.9.10	TVersionStringFileInfo.Clear	198
28.9.11	TVersionStringFileInfo.Delete	198
28.9.12	TVersionStringFileInfo.Count	198
28.9.13	TVersionStringFileInfo.Items	198
28.10	TVersionStringTable	199
28.10.1	Description	199
28.10.2	Method overview	199
28.10.3	Property overview	199
28.10.4	TVersionStringTable.Create	200
28.10.5	TVersionStringTable.Destroy	200
28.10.6	TVersionStringTable.Add	200
28.10.7	TVersionStringTable.Clear	201
28.10.8	TVersionStringTable.Delete	201
28.10.9	TVersionStringTable.Name	201
28.10.10	TVersionStringTable.Count	201

28.10.1	IVersionStringTable.Keys	202
28.10.12	IVersionStringTable.ValuesByIndex	202
28.10.13	IVersionStringTable.Values	202
28.11	TVersionVarFileInfo	203
28.11.1	Description	203
28.11.2	Method overview	203
28.11.3	Property overview	203
28.11.4	TVersionVarFileInfo.GetCount	203
28.11.5	TVersionVarFileInfo.GetItem	203
28.11.6	TVersionVarFileInfo.SetItem	203
28.11.7	TVersionVarFileInfo.Create	203
28.11.8	TVersionVarFileInfo.Destroy	204
28.11.9	TVersionVarFileInfo.Add	204
28.11.10	TVersionVarFileInfo.Clear	204
28.11.11	IVersionVarFileInfo.Delete	204
28.11.12	TVersionVarFileInfo.Count	204
28.11.13	TVersionVarFileInfo.Items	205
<b>29</b>	<b>Reference for unit 'winpeimagereader'</b>	<b>206</b>
29.1	Used units	206
29.2	Overview	206
29.3	TWinPEImageResourceReader	206
29.3.1	Description	206
29.3.2	Method overview	207
29.3.3	TWinPEImageResourceReader.CheckDosStub	207
29.3.4	TWinPEImageResourceReader.CheckPESignature	207
29.3.5	TWinPEImageResourceReader.GetExtensions	207
29.3.6	TWinPEImageResourceReader.GetDescription	207
29.3.7	TWinPEImageResourceReader.Load	207
29.3.8	TWinPEImageResourceReader.CheckMagic	207
29.3.9	TWinPEImageResourceReader.Create	207
29.3.10	TWinPEImageResourceReader.Destroy	208

## About this guide

This document describes all constants, types, variables, functions and procedures as they are declared in the units that come standard with the FCL-res (Free Pascal Resource support).

Throughout this document, we will refer to functions, types and variables with `typewriter` font. Functions and procedures have their own subsections, and for each function or procedure we have the following topics:

**Declaration** The exact declaration of the function.

**Description** What does the procedure exactly do ?

**Errors** What errors can occur.

**See Also** Cross references to other related functions/commands.

## 0.1 Introduction

This package contains a library to easily work with Microsoft Windows resources in a cross-platform way.

Classes are provided to create, load and write resources from/to different file formats in a transparent way, and to handle most common resource types without having to deal with their internal format.

Whenever possible data caching is performed, helped by a copy-on-write mechanism. This improves performance especially when converting big resources from a file format to another.

Since `fcl-res` architecture is extensible, it's always possible to extend the library with custom resource types or new file readers/writers.

Please note that resources aren't limited to Windows platform: Free Pascal can use them also on ELF and Mach-O targets. Moreover, this library can be useful for cross-compilation purposes even on other targets.

It is highly recommended to read Basic Usage (??) topic if you are approaching this library for the first time.

## 0.2 Basic Usage

### Resource files and TResources class

One of the most important classes is `TResources` (??) class, contained in `resource` (??) unit, which represents a format-independent view of a resource file. In fact, while single resources are important, they are of little use alone, since they can't be read or written to file directly: they need to be contained in a `TResources` (??) object.

`TResources` (??) provides methods to read itself from a file or stream, using specific objects that are able to read resource data from such a stream: these are the so called *resource readers*, that descend from `TAbstractResourceReader` (??).

There are also *resource writers* that do the opposite, and that descend from `TAbstractResourceWriter` (??).

Usually readers and writers register themselves with `TResources` (??) in the `initialization` section of the unit they are implemented in, so you only need to add a certain unit to your program `uses` clause to let `TResources` (??) "know" about a particular file format.

Let's see a very simple example: a program that converts a `.res` file to an object file in COFF format (the object file format used by Microsoft Windows).

```

program res1;

{$mode objfpc}

uses
  Classes, SysUtils, resource, resreader, coffwriter;

var
  resources : TResources;
begin
  resources:=TResources.Create;
  resources.LoadFromFile('myresource.res');
  resources.WriteToFile('myobject.o');
  resources.Free;
end.

```

As you can see, the code is trivial. Note that `resreader` and `coffwriter` units were added to the `uses` clause of the program: this way, the resource reader for `.res` files and the resource writer for COFF files have been registered, letting the `resources` object know how to handle these file types.

There are cases where one doesn't want to let the `TResources` (??) object to choose readers and writers by itself. In fact, while generally it is a good idea to let `TResources` (??) probe all readers it knows to find one able to read the input file, this isn't true when it comes to write files: writers are selected based on the file extension, so if you are trying to write a file with `.o` extension you can't be sure about which writer will be selected: it could be the COFF or the ELF writer (it depends on which writer gets registered first). Moreover, writers generally make an object file for the host architecture, so if you are running the program on a i386 machine it will produce a COFF or ELF file for i386.

The solution is to provide `TResources` (??) with a specific writer. In the following example the reader is automatically chosen among various readers, and we use a specific writer to produce an ELF file for SPARC.

```

program res2;

{$mode objfpc}

uses
  Classes, SysUtils, resource,
  resreader, coffreader, elfreader, winpeimagereader, //readers
  elfwriter, elfconsts;

var
  resources : TResources;
  writer : TElfResourceWriter;
begin
  resources:=TResources.Create;
  resources.LoadFromFile(paramstr(1));
  writer:=TElfResourceWriter.Create;
  writer.MachineType:=emtsparc;
  resources.WriteToFile(ChangeFileExt(paramstr(1),'.o'),writer);
  resources.Free;
  writer.Free;
end.

```

Note that the file to convert is taken from the command line. Its format is automatically detected among res (resreader (??)), coff (coffreader (??)), elf (elfreader (??)), PE (winpeimagereader (??), e.g. a Windows exe or dll), and is written as an ELF file for SPARC. Note that we had to use elfconsts (??) unit since we used emtsparc (??) constant to specify the machine type of the object file to generate.

With a small change to the above program we can let the user know which reader was selected to read the input file: we can use TResources.FindReader (??) class method to obtain the appropriate reader for a given stream.

```
program res3;

{$mode objfpc}

uses
  Classes, SysUtils, resource,
  resreader, coffreader, elfreader, winpeimagereader, //readers
  elfwriter, elfconsts;

var
  resources : TResources;
  writer : TElfResourceWriter;
  reader : TAbstractResourceReader;
  inFile : TFileStream;
begin
  resources:=TResources.Create;
  inFile:=TFileStream.Create(paramstr(1), fmOpenRead or fmShareDenyNone);
  reader:=TResources.FindReader(inFile);
  writeln('Selected reader: ', reader.Description);
  resources.LoadFromStream(inFile, reader);
  writer:=TElfResourceWriter.Create;
  writer.MachineType:=emtsparc;
  resources.WriteToFile(ChangeFileExt(paramstr(1), '.o'), writer);
  resources.Free;
  reader.Free;
  writer.Free;
  inFile.Free;
end.
```

Output example:

```
user@localhost:~$ ./res3 myresource.res
Selected reader: .res resource reader
user@localhost:~$
```

### Single resources

You can do more with resources than simply converting between file formats.

TResources.Items (??) property provides a simple way to access all resources contained in the TResources (??) object.

In the following example we read a resource file and then dump each resource data in a file whose name is built from type and name of the dumped resource.

```
program res4;
```

```
{ $mode objfpc }

uses
  Classes, SysUtils, resource, resreader;

var
  resources : TResources;
  dumpFile : TFileStream;
  i : integer;
  fname : string;
begin
  resources:=TResources.Create;
  resources.LoadFromFile('myresource.res');
  for i:=0 to resources.Count-1 do
    begin
      fname:=resources[i]._Type.Name+'_'+resources[i].Name.Name;
      dumpFile:=TFileStream.Create(fname, fmCreate or fmShareDenyWrite);
      dumpFile.CopyFrom(resources[i].RawData, resources[i].RawData.Size);
      dumpFile.Free;
    end;
  resources.Free;
end.
```

This code simply copies the content of each resource's `RawData` (??) stream to a file stream, whose name is *resourcetype\_resourcename*.

Resource raw data isn't always what one expected, however. While some resource types simply contain a copy of a file in their raw data, other types do some processing, so that dumping raw data doesn't result in a file in the format one expected.

E.g. a resource of type `RT_MANIFEST` (??) is of the former type: its raw data is like an XML manifest file. On the other hand, in a resource of type `RT_BITMAP` (??) the `RawData` (??) stream isn't like a BMP file.

For this reason, several classes (descendants of `TAbstractResource` (??)) are provided to handle the peculiarities of this or that resource type. Much like it's done with readers and writers, resource classes can be registered: adding the unit that contains a resource class to the `uses` clause of your program registers that class. This way, when resources are read from a file, they are created with the class that is registered for their type (the class responsible to do this is `TResourceFactory` (??), but probably you won't need to use it unless you're implementing a new resource reader or resource class).

In the following example, we read a resource file and then dump data of each resource of type `RT_BITMAP` (??) as a BMP file.

```
program res5;

{ $mode objfpc }

uses
  Classes, SysUtils, resource, resreader, bitmapresource;

var
  resources : TResources;
  dumpFile : TFileStream;
```



```

    i : integer;
    fname : string;
begin
    resources:=TResources.Create;
    resources.LoadFromFile('myresource.res');
    for i:=0 to resources.Count-1 do
        if resources[i] is TBitmapResource then
            with resources[i] as TBitmapResource do
                begin
                    fname:=Name.Name+'.bmp';
                    dumpFile:=TFileStream.Create(fname, fmCreate or fmShareDenyWrite);
                    dumpFile.CopyFrom(BitmapData, BitmapData.Size);
                    dumpFile.Free;
                end;
            end;
        resources.Free;
    end.

```

Note that we included `bitmapresource` (??) in the `uses` clause of our program. This way, resources of type `RT_BITMAP` (??) are created from `TBitmapResource` (??) class. This class provides a stream, `BitmapData` (??) that allows resource raw data to be accessed as if it was a bmp file.

We can of course do the opposite. In the following code we are creating a manifest resource from `manifest.xml` file.

```

program res6;

{$mode objfpc}

uses
    Classes, SysUtils, resource, reswriter;

var
    resources : TResources;
    inFile : TFileStream;
    res : TGenericResource;
    rname, rtype : TResourceDesc;
begin
    inFile:=TFileStream.Create('manifest.xml', fmOpenRead or fmShareDenyNone);
    rtype:=TResourceDesc.Create(RT_MANIFEST);
    rname:=TResourceDesc.Create(1);
    res:=TGenericResource.Create(rtype, rname);
    rtype.Free; //no longer needed
    rname.Free;
    res.SetCustomRawDataStream(inFile);
    resources:=TResources.Create;
    resources.Add(res);
    resources.WriteToFile('myresource.res');
    resources.Free; //frees res as well
    inFile.Free;
end.

```

Note that resources of type `RT_MANIFEST` (??) contain a straight copy of a xml file, so `TGenericResource` (??) class fits our needs. `TGenericResource` (??) is a basic implementation of `TAbstractResource` (??). It is the default class used by `TResourceFactory` (??) when it must create a resource whose type wasn't registered with any resource class.

Please note that instead of copying `inFile` contents to `RawData (??)` we used `SetCustomRawDataStream (??)` method: it sets a stream as the underlying stream for `RawData (??)`, so that when final resource file is written, data is read directly from the original file.

Let's see a similar example, in which we use a specific class instead of `TGenericResource (??)`. In the following code we are creating a resource containing the main program icon, which is read from `mainicon.ico` file.

```
program res7;

{$mode objfpc}

uses
  Classes, SysUtils, resource, reswriter, groupiconresource;

var
  resources : TResources;
  inFile : TFileStream;
  iconres : TGroupIconResource;
  name : TResourceDesc;
begin
  inFile:=TFileStream.Create('mainicon.ico',fmOpenRead or fmShareDenyNone);
  name:=TResourceDesc.Create('MAINICON');
  //type is always RT_GROUP_ICON for this resource class
  iconres:=TGroupIconResource.Create(nil,name);
  iconres.SetCustomItemDataStream(inFile);
  resources:=TResources.Create;
  resources.Add(iconres);
  resources.WriteToFile('myicon.res');
  resources.Free; //frees iconres as well
  inFile.Free;
  name.Free;
end.
```

In this program we created a new `TGroupIconResource (??)` with 'MAINICON' as name, and we loaded its contents from file 'mainicon.ico'. Please note that `RT_GROUP_ICON (??)` resource raw data doesn't contain a .ico file, so we have to write to `ItemData (??)` which is a ico-like stream. As we did for `res6` program, we tell the resource to use our stream as the underlying stream for resource data: the only difference is that we are using `TGroupResource.SetCustomItemDataStream (??)` instead of `TAbstractResource.SetCustomRawDataStream (??)` method, for obvious reasons.

### Other resource types

There are other resource types that allow to easily deal with resource data. E.g. `TVersionResource (??)` makes it easy to create and read version information for Windows executables and dlls, `TStringTableResource (??)` deals with string tables, and so on.

### Data caching

Whenever possible, `fcl-res` tries to avoid to duplicate data. Generally a reader doesn't copy resource data from the original stream to `RawData (??)` stream: instead, it only informs the resource about where its raw data is in the original stream. `RawData (??)` uses a caching system so that it appears as a stream while it only redirects operations to its underlying stream, with a copy-on-write mechanism. Of course this behaviour can be controlled by the user. For further information, see `TAbstractResource (??)` and `TAbstractResource.RawData (??)`.

### 0.3 How to implement a new resource class

**Remark:** This chapter assumes you have some experience in using this library.

#### Some considerations

Usually, a specific resource class is needed when resource data is encoded in a specific binary format that makes working with `RawData` (??) uncomfortable.

However, there aren't many reasons to design a new binary format requiring a specific resource class: the classes provided with this package exist for compatibility with Microsoft Windows, but in the general case one should avoid such approach.

In Microsoft Windows, some resource types have a specific format, and the operating system supports them at runtime making it easy to access that kind of data: e.g. icons and bitmaps are stored in resources in a format that is slightly different from the one found in regular files, but the operating system allows the user to easily load them using `LoadImage` function, without having to deal with their internal format. Other resource types are used to obtain information about the executable: `RT_VERSION` (??) resource type and `RT_GROUP_ICON` (??) contain version information and program icon that can be displayed in Windows Explorer, respectively.

Using this kind of resources in a cross-platform perspective doesn't make much sense however, since there is no support by other operating systems for these types of resources (and for resources in general), and this means that it's up to you to provide support at runtime for these binary formats. So if you need to store images as resources it's better to use `TGenericResource` (??) and store an image in PNG format (for instance), which can be read by existing libraries at runtime, instead of creating a `RT_BITMAP` (??) resource with `TBitmapResource` (??), since libraries that read BMP files can't handle that resource contents.

New resource classes thus make sense when you want to add support for existing Windows-specific resources, e.g. because you are writing a resource compiler or editor, but in the general case they should be avoided.

Now that you've been warned, let's start with the topic of this chapter.

#### How to implement a new resource class

A resource class is a descendant of `TAbstractResource` (??), and it's usually implemented in a unit named `typeresource`, where *type* is resource type.

If you are implementing a new resource class, you are doing it to provide additional methods or properties to utilize resource data. Your resource class must thus be able to read its `RawData` (??) stream format and write data back to it when it is requested to do so.

Generally, your class shouldn't create private objects, records or memory buffers to provide these specific means of accessing data until it's requested to do so (lazy loading), and it should free these things when it is requested to write back data to the `RawData` (??) stream.

We'll see these points in more detail, using `TAcceleratorsResource` (??) as an example.

`TAcceleratorsResource` (??) holds a collection of accelerators. An accelerator is a record defined as follows:

```
type
  TAccelerator = packed record
    Flags : word;
    Ansi : word;
    Id : word;
    padding : word;
  end;
```

The resource simply contains accelerators, one immediately following the other. Last accelerator

must have \$80 in its flags.

To provide easy access to the elements it contains, our accelerator resource class exposes these methods and properties in its public section:

```
procedure Add(aItem : TAccelerator);
procedure Clear;
procedure Delete(aIndex : integer);
property Count : integer read GetCount;
property Items[index : integer] : TAccelerator read GetItem write SetItem; default;
```

We must also implement abstract methods (and an abstract constructor) of TAbstractResource (??):

```
protected
    function GetType : TResourceDesc; override;
    function GetName : TResourceDesc; override;
    function ChangeDescTypeAllowed(aDesc : TResourceDesc) : boolean; override;
    function ChangeDescValueAllowed(aDesc : TResourceDesc) : boolean; override;
    procedure NotifyResourcesLoaded; override;
public
    constructor Create(aType, aName : TResourceDesc); override;
    procedure UpdateRawData; override;
```

The protected methods are very easy to implement, so let's start from them. For GetType (??) and GetName (??), we need to add two private fields, fType and fName, of type TResourceDesc (??). We create them in the constructor and destroy them in the destructor. Type will always be RT\_ACCELERATOR (??). We make the parameterless constructor of TAbstractResource (??) public, using 1 as the resource name, while in the other constructor we use the name passed as parameter, ignoring the type (since it must always be RT\_ACCELERATOR (??)).

So, GetType (??), GetName (??), the constructors and the destructor are implemented as follows:

```
function TAcceleratorsResource.GetType: TResourceDesc;
begin
    Result:=fType;
end;

function TAcceleratorsResource.GetName: TResourceDesc;
begin
    Result:=fName;
end;

constructor TAcceleratorsResource.Create;
begin
    inherited Create;
    fType:=TResourceDesc.Create(RT_ACCELERATOR);
    fName:=TResourceDesc.Create(1);
    SetDescOwner(fType);
    SetDescOwner(fName);
end;

constructor TAcceleratorsResource.Create(aType, aName: TResourceDesc);
begin
    Create;
    fName.Assign(aName);
```

```
end;

destructor TAcceleratorsResource.Destroy;
begin
    fType.Free;
    fName.Free;
    inherited Destroy;
end;
```

Note that we used `SetDescOwner` (??) to let type and name know the resource that owns them.

Now `ChangeDescTypeAllowed` (??) and `ChangeDescValueAllowed` (??) come. As we said, resource type must be `RT_ACCELERATOR` (??), always. Thus, we only allow name to change value or type:

```
function TAcceleratorsResource.ChangeDescTypeAllowed(aDesc: TResourceDesc) : boolean;
begin
    Result:=aDesc=fName;
end;

function TAcceleratorsResource.ChangeDescValueAllowed(aDesc: TResourceDesc) : boolean;
begin
    Result:=aDesc=fName;
end;
```

`NotifyResourcesLoaded` (??) is called by `TResources` (??) when it finishes loading all resources. Since we are not interested in this fact, we simply leave this method empty. This method is useful for resources that "own" other resources, like `TGroupIconResource` (??) and `TGroupCursorResource` (??) (note: you should **not** implement resource types that depend on other resources: it complicates things a lot and gives you a lot of headaches).

Now, let's see the more interesting - and more difficult - part: providing an easy way to deal with accelerators.

As we said earlier, we must implement some methods and properties to do so. Surely we'll need a list to hold pointers to accelerator records, but we must think a little bit about how this list is created, populated, written to `RawData` (??) and so on.

When the object is created, we don't have to create (yet) single accelerator records, as said before; but if the user tries to access them we must do it. If the object is created and its `RawData` (??) contains data (e.g. because a reader has created the resource when loading a resource file) and the user tries to access an accelerator, we must create accelerators from `RawData` (??) contents. So, until a user tries to access accelerators our class doesn't do anything, while when the user does so it "lazy-loads" data, or creates empty structures if `RawData` (??) is empty.

When data is loaded, `RawData` (??) contents aren't considered anymore. When, however, our resource is requested to update `RawData` (??) (that is, when `UpdateRawData` (??) method is invoked), our "lazy-loaded" data must be freed. In fact, a user could ask our resource to update raw data, then he/she could modify it directly and then could use our resource's specialized methods and properties to do further processing: for this reason, when `RawData` (??) is written, other buffered things must be freed, so that they'll be created again from `RawData` (??) if needed.

Note that other resource classes could behave differently: e.g. `TBitmapResource` (??) uses a copy-on-write mechanism on top of `RawData` (??) to insert a BMP file header at the beginning of the stream, but it doesn't copy `RawData` (??) contents whenever possible.

Coming back to our `TAcceleratorsResource` (??) example, let's see how to implement this behaviour.

Let's add a `fList` field in the `private` section of our class:

```
fList : TFPList;
```

In the constructor, we set this field to `nil`: we use it to check if data has been loaded from `RawData` (??) or not. Consequently in the destructor we'll free the list only if it's not `nil`:

```
destructor TAcceleratorsResource.Destroy;
begin
  fType.Free;
  fName.Free;
  if fList<>nil then
    begin
      Clear;
      fList.Free;
    end;
  inherited Destroy;
end;
```

(we did not implement `Clear` method yet: we'll see it later).

We said that our resource must load data only when needed; to do this we add a private method, `CheckDataLoaded` that ensures that data is loaded. This method is called by whatever method needs to operate on the list: if data has already been loaded it will quickly return, otherwise it will load data.

```
procedure TAcceleratorsResource.CheckDataLoaded;
var acc : TAccelerator;
    tot, i : integer;
    p : PAccelerator;
begin
  if fList<>nil then exit;
  fList:=TFPList.Create;
  if RawData.Size=0 then exit;
  RawData.Position:=0;
  tot:=RawData.Size div 8;
  for i:=1 to tot do
    begin
      RawData.ReadBuffer(acc, sizeof(acc));
      GetMem(p, sizeof(TAccelerator));
      p^:=acc;
      fList.Add(p);
    end;
  end;
```

If `fList` is not `nil` data is already loaded, so exit. Otherwise, create the list. If `RawData` (??) is empty we don't need to load anything, so exit. Otherwise allocate room for accelerators, read them from the stream, and add them to the list.

Note that if we are running on a big endian system we should swap the bytes we read, e.g. calling `SwapEndian` function, but for simplicity this is omitted.

The counterpart of `CheckDataLoaded` is `UpdateRawData` (??). When it is called, data from the list must be written back to `RawData` (??), and the list and its contents must be freed:

```
procedure TAcceleratorsResource.UpdateRawData;
var acc : TAccelerator;
```

```

        i : integer;
begin
    if fList=nil then exit;
    RawData.Size:=0;
    RawData.Position:=0;

    for i:=0 to fList.Count-1 do
    begin
        acc:=PAccelerator(fList[i])^;
        // $80 means 'this is the last entry', so be sure only the last one has this bit
        if i=Count-1 then acc.Flags:=acc.Flags or $80
        else acc.Flags:=acc.Flags and $7F;
        RawData.WriteBuffer(acc,sizeof(acc));
    end;
    Clear;
    FreeAndNil(fList);
end;

```

If `fList` is `nil` data hasn't been loaded, so `RawData` (??) is up to date, so exit. Otherwise, write each accelerator (ensuring that only last one has \$80 flag set), clear the list, free it and set it to `nil`. Again, if we are on a big endian system we should swap each accelerator contents before writing it, but for simplicity this is omitted.

Other methods we named earlier (`Add`, `Delete`, `Clear`) are trivial to implement: remember only to call `CheckDataLoaded` before doing anything. The same is true for accessor methods of relevant properties (`Count`, `Items`).

If you are curious, you can check the full implementation of `TAcceleratorsResource` (??) looking at source code.

## 0.4 How to implement a new resource reader

**Remark:** This chapter assumes you have some experience in using this library.

We'll see how to implement a reader for a new resource file format. A resource reader is a descendant of `TAbstractResourceReader` (??), and it's usually implemented in a unit named `namereader`, where *name* is file format name.

Suppose we must write a reader for file format *foo*; we could start with a unit like this:

```

unit fooreader;

{$MODE OBJFPC} {$H+}

interface

uses
    Classes, SysUtils, resource;

type
    TFooResourceReader = class(TAbstractResourceReader)
    protected
        function GetExtensions : string; override;
        function GetDescription : string; override;
        procedure Load(aResources : TResources; aStream : TStream); override;
    end;

```

```
    function CheckMagic(aStream : TStream) : boolean; override;
public
    constructor Create; override;
end;

implementation

function TFooResourceReader.GetExtensions: string;
begin

end;

function TFooResourceReader.GetDescription: string;
begin

end;

procedure TFooResourceReader.Load(aResources: TResources; aStream: TStream);
begin

end;

function TFooResourceReader.CheckMagic(aStream: TStream): boolean;
begin

end;

constructor TFooResourceReader.Create;
begin

end;

initialization
    TResources.RegisterReader('.foo', TFooResourceReader);

end.
```

**Note that in the initialization section, TFooResourceReader is registered for extension .foo.**

**We must implement abstract methods of TAbstractResourceReader (??). Let's start with the simpler ones, GetExtensions (??) and GetDescription (??).**

```
function TFooResourceReader.GetExtensions: string;
begin
    Result:='.foo';
end;

function TFooResourceReader.GetDescription: string;
begin
    Result:='FOO resource reader';
end;
```

**Now let's see CheckMagic (??) method. This method is called with a stream as a parameter, and**



the reader must return `true` if it recognizes the stream as a valid one. Usually this means checking some magic number or header.

```
function TFooResourceReader.CheckMagic(aStream: TStream): boolean;
var signature : array[0..3] of char;
begin
    Result:=false;
    try
        aStream.ReadBuffer(signature[0], 4);
    except
        on e : EReadError do exit;
    end;
    Result:=signature='FOO*';
end;
```

Suppose our foo files start with a 4-byte signature `'FOO*'`. This method checks the signature and returns `true` if it is verified. Note that it catches `EReadError` exception raised by `TStream`: this way, if the stream is too short it returns `false` (as it should, since magic is not valid) instead of letting the exception to propagate.

Now let's see `Load` (??). This method must read the stream and create resources in the `TResources` (??) object, with information about their name, type, position and size of their raw data, and so on.

```
procedure TFooResourceReader.Load(aResources: TResources; aStream: TStream);
begin
    if not CheckMagic(aStream) then
        raise EResourceReaderWrongFormatException.Create('');
    try
        ReadResources(aResources, aStream);
    except
        on e : EReadError do
            raise EResourceReaderUnexpectedEndOfStreamException.Create('');
        end;
    end;
end;
```

First of all, this method checks file magic number, calling `CheckMagic` (??) method we already implemented. This is necessary since `CheckMagic` (??) is not called before `Load` (??): `CheckMagic` (??) is invoked by `TResources` (??) when probing a stream, while `Load` (??) is invoked when loading resources (so if the user passed a reader object to a `TResources` (??) object, `CheckMagic` (??) is never called). Note also that the stream is always at its starting position when these methods are called.

If magic number is ok, our method invokes another method to do the actual loading. If during this process the stream can't be read, an `EResourceReaderUnexpectedEndOfStreamException` (??) exception is raised.

So, let's implement the private method which will load resources.

Suppose that our foo format is very simple:

- the header is made by the 4-byte signature we already saw, a longword holding the number of resources in the file, and other 8 bytes of padding.
- each resource has a 16-byte header containing:
  - a longword for the resource type (only IDs are allowed for types)
  - a longword for the resource name (only IDs are allowed for names)

- a longword for the language ID
- a longword for the size of the resource data
- after the resource header immediately comes the resource data, possibly padded so that it ends on a 4 byte boundary.
- file format is little-endian

To start with, our method will be:

```

procedure TFooResourceReader.ReadResources(aResources: TResources; aStream: TStream)
var Count, i: longword;
    aType, aName, aLangID : longword;
    aDataSize : longword;
begin
    //read remaining file header
    aStream.ReadBuffer(Count, sizeof(Count));
    aStream.Seek(8, soFromCurrent);

    for i:=1 to Count do
    begin
        //read resource header
        aStream.ReadBuffer(aType, sizeof(aType));
        aStream.ReadBuffer(aName, sizeof(aName));
        aStream.ReadBuffer(aLangID, sizeof(aLangID));
        aStream.ReadBuffer(aDataSize, sizeof(aDataSize));

    end;
end;

```

Since in Load (??) we called CheckMagic (??), which read the first 4 bytes of the header, we must read the remaining 12: we read the number of resources, and we skip the other 8 bytes of padding.

Then, for each resource, we read the resource header. Note that if we are running on a big endian system we should swap the bytes we read, e.g. calling SwapEndian function, but for simplicity this is omitted.

Now, we should create a resource. Of which class? Well, we must use resfactory (??) unit. In fact it contains TResourceFactory (??) class, which is an expert in creating resources of the right class: when the user adds a unit containing a resource class to the uses clause of its program, the resource class registers itself with TResourceFactory (??). This way it knows how to map resource types to resource classes.

We need to have type and name of the resource to create as TResourceDesc (??) objects: instead of creating and destroying these objects for each resource, we'll create a couple in the creator of our reader and we'll destroy them in the destructor, so that they will live for the whole life of our reader. Let's name them workType and workName.

Our code becomes:

```

uses
    resfactory;

procedure TFooResourceReader.ReadResources(aResources: TResources; aStream: TStream)
var Count, i: longword;
    aType, aName, aLangID : longword;

```

```

        aDataSize : longword;
        aRes : TAbstractResource;
begin
    //read remaining file header
    aStream.ReadBuffer(Count, sizeof(Count));
    aStream.Seek(8, soFromCurrent);

    for i:=1 to Count do
    begin
        //read resource header
        aStream.ReadBuffer(aType, sizeof(aType));
        aStream.ReadBuffer(aName, sizeof(aName));
        aStream.ReadBuffer(aLangID, sizeof(aLangID));
        aStream.ReadBuffer(aDataSize, sizeof(aDataSize));

        //create the resource
        workType.ID:=aType;
        workName.ID:=aName;
        aRes:=TResourceFactory.CreateResource(workType, workName);
        SetDataSize(aRes, aDataSize);
        SetDataOffset(aRes, aStream.Position);
        aRes.LangID:=aLangID;

    end;
end;

```

Note that after the resource has been created we set its data size and data offset. Data offset is the current position in the stream, since in our FOO file format resource data immediately follows resource header.

What else do we need to do? Of course we must create RawData (??) stream for our resource, so that raw data can be accessed with the caching mechanism. We will create a TResourceDataStream (??) object, telling it which resource and stream it is associated to, which its size will be and which class its underlying cached stream must be created from.

So we add resdatastream (??) to the uses clause, declare another local variable

```
aRawData : TResourceDataStream;
```

and add these lines in the for loop

```

aRawData:=TResourceDataStream.Create(aStream, aRes, aRes.DataSize, TCachedResourceDataS
SetRawData(aRes, aRawData);

```

That is, aRawData will create its underlying stream as a TCachedResourceDataStream (??) over the portion of aStream that starts at current position and ends after aRes.DataSize bytes.

We almost finished: now we must add the newly created resource to the TResources (??) object and move stream position to the next resource header. Complete code for ReadResources method is:

```

procedure TFooResourceReader.ReadResources(aResources: TResources; aStream: TStream)
var Count, i: longword;
    aType, aName, aLangID : longword;
    aDataSize : longword;
    aRes : TAbstractResource;

```

```

        aRawData : TResourceDataStream;
begin
    //read remaining file header
    aStream.ReadBuffer(Count,sizeof(Count));
    aStream.Seek(8,soFromCurrent);

    for i:=1 to Count do
    begin
        //read resource header
        aStream.ReadBuffer(aType,sizeof(aType));
        aStream.ReadBuffer(aName,sizeof(aName));
        aStream.ReadBuffer(aLangID,sizeof(aLangID));
        aStream.ReadBuffer(aDataSize,sizeof(aDataSize));

        //create the resource
        workType.ID:=aType;
        workName.ID:=aName;
        aRes:=TResourceFactory.CreateResource(workType,workName);
        SetDataSize(aRes,aDataSize);
        SetDataOffset(aRes,aStream.Position);
        aRes.LangID:=aLangID;

        //set raw data
        aRawData:=TResourceDataStream.Create(aStream,aRes,aRes.DataSize,TCachedResourceD
        SetRawData(aRes,aRawData);

        //add to aResources
        try
            aResources.Add(aRes);
        except
            on e : EResourceDuplicateException do
            begin
                aRes.Free;
                raise;
            end;
        end;

        //go to next resource header
        aStream.Seek(aDataSize,soFromCurrent);
        Align4Bytes(aStream);
    end;
end;

```

Align4Bytes is a private method (not shown for simplicity) that sets stream position to the next multiple of 4 if needed, since FOO file format specifies that resource data must be padded to end on a 4 byte boundary.

**Note:** We have used Add (??) method to populate the TResources (??) object. More complex file formats store resources in a tree hierarchy; since TResources (??) internally stores resources in this way too, a reader can choose to acquire a reference to the internal tree used by the TResources (??) object (see TAbstractResourceReader.GetTree (??)), populate it and notify the TResources (??) object about the added resources (see TAbstractResourceReader.AddNoTree (??)). For these file formats resources can be loaded faster, since there is no overhead involved in keeping a separate resource tree in the reader.

That's all. Now you should be able to create a real resource reader.

## 0.5 How to implement a new resource writer

**Remark:** This chapter assumes you have some experience in using this library.

We'll see how to implement a writer for a new resource file format. A resource writer is a descendant of `TAbstractResourceWriter` (??), and it's usually implemented in a unit named `namewriter`, where *name* is file format name.

Suppose we must write a writer for file format *foo*; we could start with a unit like this:

```
unit foowriter;

{$MODE OBJFPC} {$H+}

interface

uses
    Classes, SysUtils, resource;

type
    TFooResourceWriter = class (TAbstractResourceWriter)
    protected
        function GetExtensions : string; override;
        function GetDescription : string; override;
        procedure Write(aResources : TResources; aStream : TStream); override;
    public
        constructor Create; override;
    end;

implementation

function TFooResourceWriter.GetExtensions: string;
begin

end;

function TFooResourceWriter.GetDescription: string;
begin

end;

procedure TFooResourceWriter.Write(aResources: TResources; aStream: TStream);
begin

end;

constructor TFooResourceWriter.Create;
begin

end;

initialization
```

```
TResources.RegisterWriter(' .foo', TFooResourceWriter);

end.
```

Note that in the initialization section, TFooResourceWriter is registered for extension .foo.

We must implement abstract methods of TAbstractResourceWriter (??). Let's start with the simpler ones, GetExtensions (??) and GetDescription (??).

```
function TFooResourceWriter.GetExtensions: string;
begin
    Result:=' .foo' ;
end;

function TFooResourceWriter.GetDescription: string;
begin
    Result:='FOO resource writer';
end;
```

Now let's see Write (??). This method must write all resources in the TResources (??) object to the stream.

Suppose that our foo format is very simple:

- the header is made by a 4-byte signature (FOO\*), a longword holding the number of resources in the file, and other 8 bytes of padding.
- each resource has a 16-byte header containing:
  - a longword for the resource type (only IDs are allowed for types)
  - a longword for the resource name (only IDs are allowed for names)
  - a longword for the language ID
  - a longword for the size of the resource data
- after the resource header immediately comes the resource data, possibly padded so that it ends on a 4 byte boundary.
- file format is little-endian

Our Write (??) method could be something like this:

```
procedure TFooResourceWriter.Write(aResources: TResources; aStream: TStream);
var i : integer;
begin
    WriteFileHeader(aStream, aResources);
    for i:=0 to aResources.Count-1 do
        WriteResource(aStream, aResources[i]);
    end;
```

So we must implement WriteFileHeader, which writes the 16-byte file header, and WriteResource, which writes a single resource with its header.

Let's start from the first one:

```
procedure TFooResourceWriter.WriteFileHeader(aStream: TStream; aResources: TResourceList;
var signature : array[0..3] of char;
    rescount : longword;
    padding : qword;
begin
    signature:='FOO*';
    rescount:=aResources.Count;
    padding:=0;

    aStream.WriteBuffer(signature[0],4);
    aStream.WriteBuffer(rescount,sizeof(rescount));
    aStream.WriteBuffer(padding,sizeof(padding));
end;
```

This code simply writes the file header as defined in foo format. Note that if we are running on a big endian system we should swap bytes before writing, e.g. calling `SwapEndian` function, but for simplicity this is omitted.

Now `WriteResource` comes. This method could be like this:

```
procedure TFooResourceWriter.WriteResource(aStream: TStream; aResource: TAbstractResource;
var aType : longword;
    aName : longword;
    aLangID : longword;
    aDataSize : longword;
begin
    aType:=aResource._Type.ID;
    aName:=aResource.Name.ID;
    aLangID:=aResource.LangID;
    aDataSize:=aResource.RawData.Size;

    //write resource header
    aStream.WriteBuffer(aType,sizeof(aType));
    aStream.WriteBuffer(aName,sizeof(aName));
    aStream.WriteBuffer(aLangID,sizeof(aLangID));
    aStream.WriteBuffer(aDataSize,sizeof(aDataSize));

    //write resource data
    aResource.RawData.Position:=0;
    aStream.CopyFrom(aResource.RawData,aResource.RawData.Size);

    //align data so that it ends on a 4-byte boundary
    Align4Bytes(aStream);
end;
```

We write the 16-byte resource header, and then resource data. Note that if resources have been loaded from a stream and the user didn't modify resource data, we are copying data directly from the original stream.

`Align4Bytes` is a private method (not shown for simplicity) that writes some padding bytes to the stream if needed, since FOO file format specifies that resource data must be padded to end on a 4 byte boundary. Again, we didn't consider endianness for simplicity. And finally, note that foo format only supports IDs for types and names, so if one of them is a name (that is, a string) this code might cause exceptions to be raised.

**Note:** More complex file formats store resources in a tree hierarchy; since `TResources` (??) internally stores resources in this way too, a writer can choose to acquire a reference to the internal tree used by the `TResources` (??) object (see `TAbstractResourceWriter.GetTree` (??)) and use it directly. For these file formats resources can be written faster, since there is no overhead involved in building a separate resource tree in the writer.

That's all. Now you should be able to create a real resource writer.

## 0.6 Format of resources in object files

### Introduction

This appendix describes the format in which resources are stored in object files. This doesn't apply to PECOFF file format, where a format already exists and is well described in documentation from Microsoft.

On Microsoft Windows, resources are natively supported by the operating system. On other systems, Free Pascal RTL provides access to resources, which are embedded in the executable file in the format that is here described.

This appendix doesn't describe a particular object file format implementation (e.g. ELF or Mach-O), but the layout of the sections involved in supporting resources: the way these sections are actually laid out on a file are subject to the rules of the hosting object file format.

For external resource file details, see [Description of external resource file format](#) (??)

### Conventions

In this document, data sizes are specified with pascal-style data types. They are the following:

Table 1:

Name	Meaning
<code>longword</code>	Unsigned 32 bit integer.
<code>ptruint</code>	Unsigned integer of the size of a pointer

Byte order is the one of the target machine.

All data structures in the sections must be aligned on machine boundaries (4 bytes for 32 bit machines, 8 bytes for 64 bit machines).

Note that all pointers must be valid at runtime. This means that relocations must be written to the object file so that the linker can relocate pointers to the addresses they will have at runtime. Note also that pointers to strings are really pointers, and not offsets to the beginning of the string table.

### Resource sections

Free Pascal uses two sections to store resource information:

- `fpc.resources`. This is a data section that contains all required structures. It must be writable.
- `fpc.rehandles`. This is a bss section whose size must be equal to  $(\text{total number of resources}) * (\text{size of pointer})$ . It must be writable.

The rest of this chapter will describe the contents of `fpc.resources` section.

### Resource section layout

The `fpc.resources` section consists of these parts:



- The initial header
- The resource tree, in the form of nodes
- The string table, which can be optional
- The resource data

### The initial header

The `fpc.resources` section starts with this header:

Table 2:

Name	Offset	Length	Description
rootptr	0	ptruint	Pointer to the root node.
count	4/8	longword	Total number of resources.
usedhandles	8/12	longword	Used at runtime. Set to zero in object files.
handles	12/16	ptruint	Pointer to the first byte of <code>fpc.reshandles</code> section.

### The resource tree

Immediately following the initial header, the resource tree comes. It is made up by nodes that represent resource types, names and language ids.

Data is organized so that resource information (type, name and language id) is represented by a tree: root node contains resource types, that in turn contain resource names, which contain language ids, which describe resource data.

Given a node, its sub-nodes are ordered as follows:

- First the "named" nodes (nodes that use a string as identifier) come, then the id ones (nodes that use an integer as identifier).
- Named nodes are alphabetically sorted, in ascending order.
- Id nodes are sorted in ascending order.

In the file, all sub-nodes of a node are written in the order described above. Then, all sub-nodes of the first sub-node are written, and so on.

### Example:

There are three resources:

1. a BITMAP resource with name MYBITMAP and language id \$0409
2. a BITMAP resource with name 1 and language id 0
3. a resource with type MYTYPE and name 1 and language id 0

Nodes are laid out this way (note that BITMAP resources have type 2):

```
root | MYTYPE 2 | 1 | 0 | MYBITMAP 1 | $0409 | 0
```

That is, types (MYTYPE is a string, so it comes before 2 which is BITMAP), then names for MYTYPE (1), then language id for resource 3 (0), then names for BITMAP (MYBITMAP and 1), then language id for resource 1 (\$0409), then language id for resource 2 (0).

## Node format

Table 3:

Name	Offset	Length	Description
<code>nameid</code>	0	<code>ptruint</code>	name pointer, integer id or language id
<code>ncount</code>	4/8	<code>longword</code>	named sub-nodes count
<code>idcountsize</code>	8/12	<code>longword</code>	id sub-nodes count or resource size
<code>subptr</code>	12/16	<code>ptruint</code>	pointer to first sub-node

If the node is identified by a string, `nameid` is a pointer to the null-terminated string holding the name. If it is identified by an id, `nameid` is that id. Language id nodes are always identified by and ID.

`ncount` is the number of named sub-nodes of this node (nodes that are identified by a string).

`idcountsize` is the number of id sub-nodes of this node (nodes that are identified by an integer id). For language id nodes, this field holds the size of the resource data.

`subptr` is an pointer to the first subnode of this node. Note that it allows to access every subnode of this node, since subnodes of a node always come one after the other. For language id nodes, `subptr` is the pointer to the resource data.

### The string table

The string table is used to store strings used for resource types and names. If all resources use integer ids for name and types, it may not be present in the file.

The string table simply contains null-terminated strings, one after the other.

If present, the string table always contains a 0 (zero) at the beginning. This way, the empty string is located at the first byte of the string table.

### The resource data

This part of the file contains raw resource data. As written before, all data structures must be aligned on machine boundaries, so if a resource data size is not a multiple of 4 (for 32 bit machines) or 8 (for 64 bit machines), bytes of padding must be inserted after that resource data.

### Exported symbols

Object files containing resources must export a pointer to the first byte of `fpc.resources` section. The name of this symbol is `FPC_RESSYMBOL`.

### Mach-O specific notes

`fpc.resources` and `fpc.reshandles` sections are to be contained in a `__DATA` segment.

# Chapter 1

## Reference for unit 'acceleratorsresource'

### 1.1 Used units

Table 1.1: Used units by unit 'acceleratorsresource'

Name	Page
Classes	??
resource	<a href="#">127</a>
System	??
sysutils	??

### 1.2 Overview

This unit contains `TAcceleratorsResource` ([43](#)), a `TAbstractResource` ([42](#)) descendant specialized in handling resource of type `RT_ACCELERATOR` ([42](#)).

Adding this unit to a program's `uses` clause registers class `TAcceleratorsResource` ([43](#)) for type `RT_ACCELERATOR` ([42](#)) with `TResourceFactory` ([42](#)).

### 1.3 Constants, types and variables

#### 1.3.1 Constants

`FAlt` = 16

This flag is valid only if the key is a virtual key.

`FControl` = 8

This flag is valid only if the key is a virtual key.

`FNoInvert` = 2

This flag is obsolete and is provided only for compatibility with 16 bit Windows.

`FShift = 4`

This flag is valid only if the key is a virtual key.

`FVirtKey = 1`

When this flag is set, the accelerator key is a virtual key code. Otherwise, it is a ASCII character

### 1.3.2 Types

`PAccelerator = ^TAccelerator`

A pointer to a TAccelerator record

```
TAccelerator = packed record
  Flags : Word;
  Ansi : Word;
  Id
    : Word;
  padding : Word;
end
```

A single accelerator entry in the accelerator table resource.

The key associated with the accelerator is represented by `Ansi` field: it can be a character or a virtual-key code (in the latter case, `FVirtKey` (43) flag must be active).

The accelerator is identified by the value of `id` field.

`Flags` is a combination of the following values:

- `FVirtKey` (43)
- `FShift` (43)
- `FNoInvert` (43)
- `FControl` (42)
- `FAlt` (42)

## 1.4 TAcceleratorsResource

### 1.4.1 Description

This class represents a resource of type `RT_ACCELERATOR` (42).

An accelerator table resource is a collection of accelerators (represented by `TAccelerator` (43) records).

An accelerator represents a keystroke that can be associated with some action.

This resource type is very Microsoft Windows-specific, so it might not be of interest for many users.

Methods are provided to add, delete and modify single accelerators.

**Remark:** This class doesn't allow its type to be changed to anything else than `RT_ACCELERATOR` (42). Attempts to do so result in a `EResourceDescChangeNotAllowedException` (42).

### 1.4.2 Method overview

Page	Method	Description
<a href="#">45</a>	Add	Adds a new accelerator to the table
<a href="#">44</a>	ChangeDescTypeAllowed	
<a href="#">44</a>	ChangeDescValueAllowed	
<a href="#">45</a>	Clear	Empties the accelerator table
<a href="#">45</a>	Create	Creates a new accelerator table resource
<a href="#">45</a>	Delete	Deletes an accelerator from the table
<a href="#">45</a>	Destroy	
<a href="#">44</a>	GetName	
<a href="#">44</a>	GetType	
<a href="#">44</a>	NotifyResourcesLoaded	
<a href="#">45</a>	UpdateRawData	

### 1.4.3 Property overview

Page	Properties	Access	Description
<a href="#">46</a>	Count	r	The number of accelerators in the table
<a href="#">46</a>	Items	rw	Indexed array of accelerators in the table

### 1.4.4 TAcceleratorsResource.GetType

Declaration: `function GetType : TResourceDesc; Override`

Visibility: protected

### 1.4.5 TAcceleratorsResource.GetName

Declaration: `function GetName : TResourceDesc; Override`

Visibility: protected

### 1.4.6 TAcceleratorsResource.ChangeDescTypeAllowed

Declaration: `function ChangeDescTypeAllowed(aDesc: TResourceDesc) : Boolean  
; Override`

Visibility: protected

### 1.4.7 TAcceleratorsResource.ChangeDescValueAllowed

Declaration: `function ChangeDescValueAllowed(aDesc: TResourceDesc) : Boolean  
; Override`

Visibility: protected

### 1.4.8 TAcceleratorsResource.NotifyResourcesLoaded

Declaration: `procedure NotifyResourcesLoaded; Override`

Visibility: protected

### 1.4.9 TAcceleratorsResource.Create

Synopsis: Creates a new accelerator table resource

Declaration: `constructor Create; Override`  
`constructor Create(aType: TResourceDesc; aName: TResourceDesc)`  
`; Override`

Visibility: public

Description: Please note that `aType` parameter is not used, since this class always uses `RT_ACCELERATOR` (42) as type.

### 1.4.10 TAcceleratorsResource.Destroy

Declaration: `destructor Destroy; Override`

Visibility: public

### 1.4.11 TAcceleratorsResource.UpdateRawData

Declaration: `procedure UpdateRawData; Override`

Visibility: public

### 1.4.12 TAcceleratorsResource.Add

Synopsis: Adds a new accelerator to the table

Declaration: `procedure Add(aItem: TAccelerator)`

Visibility: public

See also: `TAcceleratorsResource.Items` (46)

### 1.4.13 TAcceleratorsResource.Clear

Synopsis: Empties the accelerator table

Declaration: `procedure Clear`

Visibility: public

See also: `TAcceleratorsResource.Items` (46), `TAcceleratorsResource.Delete` (45)

### 1.4.14 TAcceleratorsResource.Delete

Synopsis: Deletes an accelerator from the table

Declaration: `procedure Delete(aIndex: Integer)`

Visibility: public

See also: `TAcceleratorsResource.Items` (46), `TAcceleratorsResource.Clear` (45)

### 1.4.15 TAcceleratorsResource.Count

Synopsis: The number of accelerators in the table

Declaration: `Property Count : Integer`

Visibility: public

Access: Read

See also: TAcceleratorsResource.Items (46)

### 1.4.16 TAcceleratorsResource.Items

Synopsis: Indexed array of accelerators in the table

Declaration: `Property Items[index: Integer]: TAccelerator; default`

Visibility: public

Access: Read,Write

Description: This property can be used to access all accelerators in the object.

**Remark:** This array is 0-based: valid elements range from 0 to Count (46)-1.

**Remark:** If you need to access RawData (42) after you added, deleted or modified accelerators, be sure to call UpdateRawData (42) first. This isn't needed however when resource is written to a stream, since TResources (42) takes care of it.

See also: TAcceleratorsResource.Count (46), TAccelerator (43)

## Chapter 2

# Reference for unit 'bitmapresource'

### 2.1 Used units

Table 2.1: Used units by unit 'bitmapresource'

Name	Page
Classes	??
resource	<a href="#">127</a>
System	??
sysutils	??

### 2.2 Overview

This unit contains [TBitmapResource \(47\)](#), a [TAbstractResource \(47\)](#) descendant specialized in handling resource of type [RT\\_BITMAP \(47\)](#).

Adding this unit to a program's `uses` clause registers class [TBitmapResource \(47\)](#) for type [RT\\_BITMAP \(47\)](#) with [TResourceFactory \(47\)](#).

### 2.3 TBitmapResource

#### 2.3.1 Description

This class represents a resource of type [RT\\_BITMAP \(47\)](#).

A bitmap resource contents is very similar to a BMP file. However some differences exists, so [RawData \(47\)](#) is not appropriate if you need to read and write BMP data. Instead, [BitmapData \(50\)](#) property gives access to a BMP file-like stream.

**Remark:** This class doesn't allow its type to be changed to anything else than [RT\\_BITMAP \(47\)](#). Attempts to do so result in a [EResourceDescChangeNotAllowedException \(47\)](#).

See also: [BitmapData \(50\)](#), [TAbstractResource.RawData \(47\)](#)



### 2.3.2 Method overview

Page	Method	Description
<a href="#">48</a>	ChangeDescTypeAllowed	
<a href="#">48</a>	ChangeDescValueAllowed	
<a href="#">49</a>	Create	Creates a new bitmap resource
<a href="#">49</a>	Destroy	
<a href="#">48</a>	GetName	
<a href="#">48</a>	GetType	
<a href="#">48</a>	NotifyResourcesLoaded	
<a href="#">49</a>	SetCustomBitmapDataStream	Sets a custom stream as the underlying stream for BitmapData
<a href="#">49</a>	UpdateRawData	

### 2.3.3 Property overview

Page	Properties	Access	Description
<a href="#">50</a>	BitmapData	r	Resource data as a BMP stream

### 2.3.4 TBitmapResource.GetType

Declaration: `function GetType : TResourceDesc; Override`

Visibility: protected

### 2.3.5 TBitmapResource.GetName

Declaration: `function GetName : TResourceDesc; Override`

Visibility: protected

### 2.3.6 TBitmapResource.ChangeDescTypeAllowed

Declaration: `function ChangeDescTypeAllowed(aDesc: TResourceDesc) : Boolean; Override`

Visibility: protected

### 2.3.7 TBitmapResource.ChangeDescValueAllowed

Declaration: `function ChangeDescValueAllowed(aDesc: TResourceDesc) : Boolean; Override`

Visibility: protected

### 2.3.8 TBitmapResource.NotifyResourcesLoaded

Declaration: `procedure NotifyResourcesLoaded; Override`

Visibility: protected

### 2.3.9 TBitmapResource.Create

Synopsis: Creates a new bitmap resource

Declaration: constructor Create; Override  
 constructor Create(aType: TResourceDesc; aName: TResourceDesc)  
 ; Override

Visibility: public

Description: Please note that aType parameter is not used, since this class always uses RT\_BITMAP (47) as type.

### 2.3.10 TBitmapResource.Destroy

Declaration: destructor Destroy; Override

Visibility: public

### 2.3.11 TBitmapResource.UpdateRawData

Declaration: procedure UpdateRawData; Override

Visibility: public

### 2.3.12 TBitmapResource.SetCustomBitmapDataStream

Synopsis: Sets a custom stream as the underlying stream for BitmapData

Declaration: procedure SetCustomBitmapDataStream(aStream: TStream)

Visibility: public

Description: This method allows the user to use a custom stream as the underlying stream for BitmapData (50). This is useful when you want a TBitmapResource (47) to be created from a bmp file for which you have a stream.

#### Sample code

This code creates a resource containing a bitmap

```
var
  aName : TResourceDesc;
  aRes : TBitmapResource;
  aFile : TFileStream;
  Resources : TResources;
begin
  Resources:=TResources.Create;
  aName:=TResourceDesc.Create('MYBITMAP');
  aRes:=TBitmapResource.Create(nil,aName); //type is always RT_BITMAP
  aName.Free; //not needed anymore
  aFile:=TFileStream.Create('mybitmap.bmp',fmOpenRead or fmShareDenyNone);
  aRes.SetCustomBitmapDataStream(aFile);
  Resources.Add(aRes);
  Resources.WriteToFile('myresource.res');

  Resources.Free; //it destroys aRes as well.
```

```
aFile.Free;  
end;
```

See also: [TBitmapResource.BitmapData \(50\)](#), [TAbstractResource.UpdateRawData \(47\)](#)

### 2.3.13 TBitmapResource.BitmapData

Synopsis: Resource data as a BMP stream

Declaration: `Property BitmapData : TStream`

Visibility: `public`

Access: `Read`

Description: [BitmapData \(50\)](#) property gives access to resource data in a BMP file-like stream, unlike [RawData \(47\)](#).

[BitmapData \(50\)](#) does not create a copy of [RawData \(47\)](#) so memory usage is generally kept limited. You can also set a custom stream as the underlying stream for [BitmapData \(50\)](#) via [SetCustomBitmapDataStream \(49\)](#), much like [SetCustomRawDataStream \(47\)](#) does for [RawData \(47\)](#). This is useful when you want a [TBitmapResource \(47\)](#) to be created from a bmp file for which you have a stream.

**Remark:** If you need to access [RawData \(47\)](#) after you modified [BitmapData \(50\)](#), be sure to call [UpdateRawData \(47\)](#) first. This isn't needed however when resource is written to a stream, since [TResources \(47\)](#) takes care of it.

See also: [TBitmapResource.SetCustomBitmapDataStream \(49\)](#), [TAbstractResource.RawData \(47\)](#), [TAbstractResource.UpdateRawData \(47\)](#)

## Chapter 3

# Reference for unit 'coffreader'

### 3.1 Used units

Table 3.1: Used units by unit 'coffreader'

Name	Page
Classes	??
cofftypes	<a href="#">54</a>
resource	<a href="#">127</a>
resourcetree	<a href="#">162</a>
System	??
sysutils	??

### 3.2 Overview

This unit contains `TCoffResourceReader` ([51](#)), a `TAbstractResourceReader` ([51](#)) descendant that is able to read COFF object files containing resources.

Adding this unit to a program's `uses` clause registers class `TCoffResourceReader` ([51](#)) with `TResources` ([51](#)).

### 3.3 TCoffResourceReader

#### 3.3.1 Description

This class provides a reader for COFF object files containing resources.

COFF is the file format used by Microsoft Windows object files. Usually resources get stored in a object file that can be given to a linker to produce an executable.

After an object file has been read, `MachineType` ([53](#)) property holds the machine type the object file was built for.

**Remark:** This reader is not able to read full PE images. Use `TWinPEImageResourceReader` ([51](#)) instead.

See also: `TCoffResourceReader.MachineType` ([53](#)), `TAbstractResourceReader` ([51](#)), `TWinPEImageResourceReader` ([51](#)), `TCoffResourceWriter` ([51](#))

**3.3.2 Method overview**

Page	Method	Description
<a href="#">52</a>	CheckMagic	
<a href="#">52</a>	Create	
<a href="#">52</a>	Destroy	
<a href="#">52</a>	GetDescription	
<a href="#">52</a>	GetExtensions	
<a href="#">52</a>	Load	

**3.3.3 Property overview**

Page	Properties	Access	Description
<a href="#">53</a>	MachineType	r	The machine type of the object file

**3.3.4 TCoffResourceReader.GetExtensions**

Declaration: `function GetExtensions : string; Override`

Visibility: `protected`

**3.3.5 TCoffResourceReader.GetDescription**

Declaration: `function GetDescription : string; Override`

Visibility: `protected`

**3.3.6 TCoffResourceReader.Load**

Declaration: `procedure Load(aResources: TResources; aStream: TStream); Override`

Visibility: `protected`

**3.3.7 TCoffResourceReader.CheckMagic**

Declaration: `function CheckMagic(aStream: TStream) : Boolean; Override`

Visibility: `protected`

**3.3.8 TCoffResourceReader.Create**

Declaration: `constructor Create; Override`

Visibility: `public`

**3.3.9 TCoffResourceReader.Destroy**

Declaration: `destructor Destroy; Override`

Visibility: `public`

### 3.3.10 TCoffResourceReader.MachineType

Synopsis: The machine type of the object file

Declaration: `Property MachineType : TCoffMachineType`

Visibility: `public`

Access: `Read`

Description: This property holds the machine type of the object file that has been read.

**Remark:** Obviously, this property is meaningful only after an object file has been read.

See also: `TCoffMachineType` ([51](#))

## Chapter 4

# Reference for unit 'cofftypes'

### 4.1 Used units

Table 4.1: Used units by unit 'cofftypes'

Name	Page
System	??

### 4.2 Overview

These types are used internally by TCoffResourceWriter ([54](#)) and TCoffResourceReader ([54](#)).  
The only type of interest for the user is TCoffMachineType ([55](#)).

### 4.3 Constants, types and variables

#### 4.3.1 Constants

```
RSRC SectName : TSectionName = '.rsrc' + #0 + #0 + #0
```

#### 4.3.2 Types

```
TCoffHeader = packed record
  Machine : Word;
  NumSects : Word;
  TimeStamp : LongWord;
  SymTablePtr : LongWord;
  SymNum : LongWord
;
  OptHdrSize : Word;
  Characteristics : Word;
end
```

```
TCoffMachineType = (cmti386, cmtarm, cmtx8664, cmtpc32aix, cmtpc64aix
)
```

Table 4.2: Enumeration values for type TCoffMachineType

Value	Explanation
cmtarm	ARM
cmti386	Intel i386
cmtpc32aix	
cmtpc64aix	
cmtx8664	AMD x86_64

This enumeration specifies the COFF machine type.

It is used by TCoffResourceWriter (54) to specify the machine type of the generated object file and by TCoffResourceReader (54) to read the machine type of the object file that has been read.

```
TCoffSectionHeader = packed record
  Name : TSectionName;
  VirtualSize
  : LongWord;
  VirtualAddress : LongWord;
  SizeOfRawData : LongWord
;
  PointerToRawData : LongWord;
  PointerToRelocations : LongWord
;
  PointerToLineNumbers : LongWord;
  NumberOfRelocations : Word
;
  NumberOfLineNumbers : Word;
  Characteristics : LongWord;
end
```

```
TCoffSectionTable = TCoffSymtableEntry
```

```
TCoffSymtableEntry = packed record
case Byte of
1: (
  Name : TSectionName
;
  Value : LongWord;
  SectionNumber : Word;
  _type : Word;
  StorageClass
  : Byte;
  NumAuxSymbol : Byte;
);
2: (
```



```

    n_name : TSectionName;
    n_value : LongWord;
    n_scnun : Word;
    n_type : Word;
    n_sclass
    : Byte;
    n_numaux : Byte;
);
end

TResDataEntry = packed record
    DataRVA : LongWord;
    Size : LongWord
    ;
    Codepage : LongWord;
    Reserved : LongWord;
end

TResDirEntry = packed record
    NameID : LongWord;
    DataSubDirRVA
    : LongWord;
end

TResDirTable = packed record
    Characteristics : LongWord;
    TimeStamp
    : LongWord;
    VerMajor : Word;
    VerMinor : Word;
    NamedEntriesCount
    : Word;
    IDEntriesCount : Word;
end

TSectionName = Array[0..7] of Char

TXCoff32SectionHeader = packed record
    s_name : TSectionName;
    s_paddr
    : LongWord;
    s_vaddr : LongWord;
    s_size : LongWord;
    s_scnptr
    : LongWord;
    s_relptr : LongWord;
    s_lnnoptr : LongWord;
    s_nreloc
    : Word;
    s_nlnno : Word;
    s_flags : LongWord;
end

```

```
TXCoffAuxSymbol32 = packed record
  x_scnlen : LongWord;
  x_parmhash
  : LongWord;
  x_snhash : Word;
  x_smtyp : Byte;
  x_smclas : Byte
  ;
  x_stab : LongWord;
  x_snstab : Word;
end
```

## Chapter 5

# Reference for unit 'coffwriter'

### 5.1 Used units

Table 5.1: Used units by unit 'coffwriter'

Name	Page
Classes	??
cofftypes	<a href="#">54</a>
resource	<a href="#">127</a>
resourcetree	<a href="#">162</a>
System	??
sysutils	??

### 5.2 Overview

This unit contains `TCoffResourceWriter` ([61](#)), a `TAbstractResourceWriter` ([58](#)) descendant that is able to write COFF object files containing resources.

Adding this unit to a program's `uses` clause registers class `TCoffResourceWriter` ([61](#)) with `TResources` ([58](#)).

### 5.3 Constants, types and variables

#### 5.3.1 Types

```
PCoffRelocation = ^TCoffRelocation
```

This type is used internally by `TCoffResourceWriter` ([61](#)).

```
TCoffRelocation = packed record
  VirtualAddress : LongWord;
  SymTableIndex
    : LongWord;
  _type : Word;
end
```

This record is used internally by TCoffResourceWriter (61).

## 5.4 TCoffRelocations

### 5.4.1 Description

This class is used internally by TCoffResourceWriter (61).

### 5.4.2 Method overview

Page	Method	Description
<a href="#">60</a>	Add	
<a href="#">60</a>	AddRelativeToSection	
<a href="#">60</a>	Clear	
<a href="#">59</a>	Create	
<a href="#">59</a>	Destroy	
<a href="#">59</a>	GetCount	
<a href="#">59</a>	GetRelocation	

### 5.4.3 Property overview

Page	Properties	Access	Description
<a href="#">60</a>	Count	r	
<a href="#">60</a>	Items	r	
<a href="#">60</a>	MachineType	rw	
<a href="#">60</a>	StartAddress	rw	

### 5.4.4 TCoffRelocations.GetCount

Declaration: `function GetCount : Integer`

Visibility: `protected`

### 5.4.5 TCoffRelocations.GetRelocation

Declaration: `function GetRelocation(index: Integer) : PCoffRelocation`

Visibility: `protected`

### 5.4.6 TCoffRelocations.Create

Declaration: `constructor Create(aMachineType: TCoffMachineType)`

Visibility: `public`

### 5.4.7 TCoffRelocations.Destroy

Declaration: `destructor Destroy; Override`

Visibility: `public`

#### 5.4.8 TCoffRelocations.Add

Declaration: procedure Add(aAddress: LongWord; aType: Word; aSymTableIndex: LongWord)

Visibility: public

#### 5.4.9 TCoffRelocations.AddRelativeToSection

Declaration: procedure AddRelativeToSection(aAddress: LongWord;  
aSectSymTableIndex: LongWord)

Visibility: public

#### 5.4.10 TCoffRelocations.Clear

Declaration: procedure Clear

Visibility: public

#### 5.4.11 TCoffRelocations.Count

Declaration: Property Count : Integer

Visibility: public

Access: Read

#### 5.4.12 TCoffRelocations.Items

Declaration: Property Items[index: Integer]: PCoffRelocation; default

Visibility: public

Access: Read

#### 5.4.13 TCoffRelocations.StartAddress

Declaration: Property StartAddress : LongWord

Visibility: public

Access: Read, Write

#### 5.4.14 TCoffRelocations.MachineType

Declaration: Property MachineType : TCoffMachineType

Visibility: public

Access: Read, Write

## 5.5 TCoffResourceWriter

### 5.5.1 Description

This class provides a writer for COFF object files containing resources.

COFF is the file format used by Microsoft Windows object files. Usually resources get stored in a object file that can be given to a linker to produce an executable.

MachineType (63) property can be used to set the machine type of the object file to generate.

See also: TCoffResourceWriter.MachineType (63), TAbstractResourceWriter (58), TCoffResourceWriter (58)

### 5.5.2 Method overview

Page	Method	Description
63	Create	
63	Destroy	
62	FixCoffHeader	
62	FixSectionHeader	
62	GetDescription	
62	GetExtensions	
62	GetFixedCoffHeader	
63	PrescanNode	
63	PrescanResourceTree	
63	Write	
62	WriteCoffStringTable	
61	WriteEmptyCoffHeader	
61	WriteEmptySectionHeader	
62	WriteRawData	
62	WriteRelocations	
62	WriteResStringTable	
63	WriteSymbolTable	

### 5.5.3 Property overview

Page	Properties	Access	Description
63	MachineType	rw	The machine type of the object file
64	OppositeEndianess	rw	

### 5.5.4 TCoffResourceWriter.WriteEmptyCoffHeader

Declaration: procedure WriteEmptyCoffHeader(aStream: TStream)

Visibility: protected

### 5.5.5 TCoffResourceWriter.WriteEmptySectionHeader

Declaration: procedure WriteEmptySectionHeader(aStream: TStream); Virtual

Visibility: protected

### 5.5.6 TCoffResourceWriter.WriteResStringTable

Declaration: procedure WriteResStringTable(aStream: TStream); Virtual

Visibility: protected

### 5.5.7 TCoffResourceWriter.WriteRawData

Declaration: procedure WriteRawData(aStream: TStream)

Visibility: protected

### 5.5.8 TCoffResourceWriter.WriteRelocations

Declaration: procedure WriteRelocations(aStream: TStream)

Visibility: protected

### 5.5.9 TCoffResourceWriter.WriteCoffStringTable

Declaration: procedure WriteCoffStringTable(aStream: TStream)

Visibility: protected

### 5.5.10 TCoffResourceWriter.GetFixedCoffHeader

Declaration: function GetFixedCoffHeader : TCoffHeader; Virtual

Visibility: protected

### 5.5.11 TCoffResourceWriter.FixCoffHeader

Declaration: procedure FixCoffHeader(aStream: TStream)

Visibility: protected

### 5.5.12 TCoffResourceWriter.FixSectionHeader

Declaration: procedure FixSectionHeader(aStream: TStream; aResources: TResources)  
; Virtual

Visibility: protected

### 5.5.13 TCoffResourceWriter.GetExtensions

Declaration: function GetExtensions : string; Override

Visibility: protected

### 5.5.14 TCoffResourceWriter.GetDescription

Declaration: function GetDescription : string; Override

Visibility: protected

#### 5.5.15 TCoffResourceWriter.PrescanNode

Declaration: `function PrescanNode(aNode: TResourceTreeNode; aNodeSize: LongWord)  
: LongWord; Virtual`

Visibility: protected

#### 5.5.16 TCoffResourceWriter.PrescanResourceTree

Declaration: `procedure PrescanResourceTree; Virtual`

Visibility: protected

#### 5.5.17 TCoffResourceWriter.Write

Declaration: `procedure Write(aResources: TResources; aStream: TStream); Override`

Visibility: protected

#### 5.5.18 TCoffResourceWriter.WriteSymbolTable

Declaration: `procedure WriteSymbolTable(aStream: TStream; aResources: TResources)  
; Virtual`

Visibility: protected

#### 5.5.19 TCoffResourceWriter.Create

Declaration: `constructor Create; Override`

Visibility: public

#### 5.5.20 TCoffResourceWriter.Destroy

Declaration: `destructor Destroy; Override`

Visibility: public

#### 5.5.21 TCoffResourceWriter.MachineType

Synopsis: The machine type of the object file

Declaration: `Property MachineType : TCoffMachineType`

Visibility: public

Access: Read, Write

Description: This property can be used to set the machine type of the object file to write.

See also: `TCoffMachineType` ([58](#))



### 5.5.2 TCoffResourceWriter.OppositeEndianess

Declaration: `Property OppositeEndianess : Boolean`

Visibility: `public`

Access: `Read,Write`

## 5.6 TCoffStringTable

### 5.6.1 Method overview

Page	Method	Description
<a href="#">64</a>	Add	
<a href="#">64</a>	Create	
<a href="#">64</a>	Delete	

### 5.6.2 Property overview

Page	Properties	Access	Description
<a href="#">64</a>	Size	r	

### 5.6.3 TCoffStringTable.Create

Declaration: `constructor Create`

Visibility: `public`

### 5.6.4 TCoffStringTable.Add

Declaration: `function Add(const S: string) : Integer; Override`

Visibility: `public`

### 5.6.5 TCoffStringTable.Delete

Declaration: `procedure Delete(Index: Integer); Override`

Visibility: `public`

### 5.6.6 TCoffStringTable.Size

Declaration: `Property Size : ptruint`

Visibility: `public`

Access: `Read`

## 5.7 TResourceStringTable

### 5.7.1 Description

This class is used internally by `TCoffResourceWriter` ([61](#)).

**5.7.2 Method overview**

Page	Method	Description
<a href="#">65</a>	Add	
<a href="#">65</a>	Clear	
<a href="#">65</a>	Create	
<a href="#">65</a>	Destroy	

**5.7.3 Property overview**

Page	Properties	Access	Description
<a href="#">65</a>	Count	r	
<a href="#">66</a>	CurrRVA	r	
<a href="#">66</a>	EndRVA	r	
<a href="#">66</a>	Items	r	
<a href="#">66</a>	StartRVA	rw	

**5.7.4 TResourceStringTable.Create**

Declaration: `constructor Create`

Visibility: `public`

**5.7.5 TResourceStringTable.Destroy**

Declaration: `destructor Destroy; Override`

Visibility: `public`

**5.7.6 TResourceStringTable.Add**

Declaration: `procedure Add(s: string)`

Visibility: `public`

**5.7.7 TResourceStringTable.Clear**

Declaration: `procedure Clear`

Visibility: `public`

**5.7.8 TResourceStringTable.Count**

Declaration: `Property Count : Integer`

Visibility: `public`

Access: `Read`

### **5.7.9 TResourceStringTable.Items**

Declaration: Property Items[index: Integer]: string; default

Visibility: public

Access: Read

### **5.7.10 TResourceStringTable.StartRVA**

Declaration: Property StartRVA : LongWord

Visibility: public

Access: Read, Write

### **5.7.11 TResourceStringTable.CurrRVA**

Declaration: Property CurrRVA : LongWord

Visibility: public

Access: Read

### **5.7.12 TResourceStringTable.EndRVA**

Declaration: Property EndRVA : LongWord

Visibility: public

Access: Read

## Chapter 6

# Reference for unit 'dfmreader'

### 6.1 Used units

Table 6.1: Used units by unit 'dfmreader'

Name	Page
Classes	??
resource	<a href="#">127</a>
System	??
sysutils	??

### 6.2 Overview

This unit contains TDfmResourceReader ([67](#)), a TAbstractResourceReader ([67](#)) descendant used to compile DFM files to resources.

Adding this unit to a program's `uses` clause registers class TDfmResourceReader ([67](#)) with TResources ([67](#)).

### 6.3 TDfmResourceReader

#### 6.3.1 Description

This class isn't a proper resource reader. It provides a quick way to create a resource file from a DFM/XFM/LFM file, similar to what Delphi does with constructs like `{ $R *.dfm }`.

This class reads a DFM, XFM or LFM file, compiles it to binary format if it isn't, and stores it in a resource of type RT\_RCDATA ([67](#)) with the name of the form specified in the DFM file.

### 6.3.2 Method overview

Page	Method	Description
<a href="#">68</a>	CheckMagic	
<a href="#">68</a>	Create	
<a href="#">68</a>	Destroy	
<a href="#">68</a>	GetDescription	
<a href="#">68</a>	GetExtensions	
<a href="#">68</a>	Load	

### 6.3.3 TDfmResourceReader.GetExtensions

Declaration: `function GetExtensions : string; Override`

Visibility: `protected`

### 6.3.4 TDfmResourceReader.GetDescription

Declaration: `function GetDescription : string; Override`

Visibility: `protected`

### 6.3.5 TDfmResourceReader.Load

Declaration: `procedure Load(aResources: TResources; aStream: TStream); Override`

Visibility: `protected`

### 6.3.6 TDfmResourceReader.CheckMagic

Declaration: `function CheckMagic(aStream: TStream) : Boolean; Override`

Visibility: `protected`

### 6.3.7 TDfmResourceReader.Create

Declaration: `constructor Create; Override`

Visibility: `public`

### 6.3.8 TDfmResourceReader.Destroy

Declaration: `destructor Destroy; Override`

Visibility: `public`

## Chapter 7

# Reference for unit 'elfconsts'

### 7.1 Used units

Table 7.1: Used units by unit 'elfconsts'

Name	Page
System	??

### 7.2 Overview

These constants are used internally by TElfResourceWriter ([69](#)) and TElfResourceReader ([69](#)).  
The only type of interest for the user is TElfMachineType ([74](#)).

### 7.3 Constants, types and variables

#### 7.3.1 Constants

EF\_IA\_64\_ABI64 = \$10

ELFCLASS32 = 1

ELFCLASS64 = 2

ELFCLASSNONE = 0

ELFDATA2LSB = 1

ELFDATA2MSB = 2

ELFDATANONE = 0

ELFMAGIC = (\$7f) + 'ELF'

ELFOSABI\_ARM = 97

ELFOSABI\_FREEBSD = 9

ELFOSABI\_LINUX = 3

ELFOSABI\_NONE = 0

EM\_386 = 3

EM\_68K = 4

EM\_ALPHA = \$9026

EM\_ARM = 40

EM\_IA\_64 = 50

EM\_MIPS = 8

EM\_MIPS\_RS3\_LE = 10

EM\_MIPS\_X = 51

EM\_NONE = 0

EM\_PPC = 20

EM\_PPC64 = 21

EM\_SPARC = 2

EM\_X86\_64 = 62

ET\_CORE = 4

ET\_DYN = 3

ET\_EXEC = 2

ET\_HIOS = \$feff

ET\_HIPROC = \$ffff

ET\_LOOS = \$fe00

ET\_LOPROC = \$ff00

ET\_NONE = 0

ET\_REL = 1

EV\_CURRENT = 1

EV\_NONE = 0

HANDLESECT\_IDX = 2

HandlesSectName = 'fpc.reshandles'

RsrcSectName = 'fpc.resources'

RSRCSECT\_IDX = 1

R\_386\_32 = 1

R\_68K\_32 = 1

R\_ALPHA\_REFQUAD = 2

R\_ARM\_ABS32 = 2



R\_IA64\_DIR64LSB = 27

R\_MIPS\_32 = 2

R\_PPC64\_ADDR64 = 38

R\_PPC\_ADDR32 = 1

R\_SPARC\_32 = 3

R\_x86\_64\_64 = 1

SHF\_ALLOC = 2

SHF\_EXECINSTR = 4

SHF\_MASKOS = 0xf0000000

SHF\_MASKPROC = 0xf0000000

SHF\_WRITE = 1

SHT\_DYNAMIC = 6

SHT\_DYNSYM = 11

SHT\_HASH = 5

SHT\_HIOS = 0xffffffff

SHT\_HIPROC = 0x7fffffff

SHT\_LOOS = 0x80000000

SHT\_LOPROC = 0x70000000

SHT\_NOBITS = 8

SHT\_NOTE = 7

SHT\_NULL = 0

SHT\_PROGBITS = 1

SHT\_REL = 9

SHT\_RELA = 4

SHT\_SHLIB = 10

SHT\_STRTAB = 3

SHT\_SYMTAB = 2

STB\_GLOBAL = 1

STB\_HIOS = 12

STB\_HIPROC = 15

STB\_LOCAL = 0

STB\_LOOS = 10

STB\_LOPROC = 13

STB\_WEAK = 2

STT\_COMMON = 5

STT\_FILE = 4

STT\_FUNC = 2

STT\_HIOS = 12

STT\_HIPROC = 15

STT\_LOOS = 10

STT\_LOPROC = 13

STT\_NOTYPE = 0

STT\_OBJECT = 1

STT\_SECTION = 3

STT\_SPARC\_REGISTER = 13

STT\_TLS = 6

### 7.3.2 Types

```
TElfMachineType = (emtnone, emtsparc, emti386, emtm68k, emtppc, emtppc64,
    ,
    , emtarm, emtarmeb, emtia64, emtx86_64, emtalphabet, emtmips,
    ,
    , emtmipsel)
```

Table 7.2: Enumeration values for type TElfMachineType

Value	Explanation
emtalphabet	DEC Alpha machine type
emtarm	ARM machine type
emtarmeb	ARM Big Endian machine type
emti386	Intel 386 machine type
emtia64	Intel IA-64 machine type
emtm68k	Motorola 68000 machine type
emtmips	
emtmipsel	
emtnone	Invalid machine type
emtppc	PowerPC machine type
emtppc64	PowerPC 64 machine type
emtsparc	Sparc machine type
emtx86_64	AMD x86_64 machine type

This enumeration specifies the ELF machine type.

It is used by TElfResourceWriter (69) to specify the machine type of the generated object file and by TElfResourceReader (69) to read the machine type of the object file that has been read.

## Chapter 8

# Reference for unit 'elfreader'

### 8.1 Used units

Table 8.1: Used units by unit 'elfreader'

Name	Page
Classes	??
elfconsts	<a href="#">69</a>
elftypes	??
resource	<a href="#">127</a>
System	??
sysutils	??

### 8.2 Overview

This unit contains `TElfResourceReader` ([76](#)), a `TAbstractResourceReader` ([75](#)) descendant that is able to read ELF object files containing resources.

Adding this unit to a program's `uses` clause registers class `TElfResourceReader` ([76](#)) with `TResources` ([75](#)).

### 8.3 `EElfResourceReaderException`

#### 8.3.1 Description

Base class for elf resource reader-related exceptions

### 8.4 `EElfResourceReaderNoSectionsException`

#### 8.4.1 Description

This exception is raised by `Load` ([75](#)) method of `TElfResourceReader` ([76](#)) when no section headers are found.

## 8.5 EElfResourceReaderNoStringTableException

### 8.5.1 Description

This exception is raised by Load (75) method of TElfResourceReader (76) when no ELF string table is found.

## 8.6 EElfResourceReaderUnknownClassException

### 8.6.1 Description

This exception is raised by Load (75) method of TElfResourceReader (76) when class field of ELF header is neither ELFCLASS32 (75) nor ELFCLASS64 (75).

## 8.7 EElfResourceReaderUnknownVersionException

### 8.7.1 Description

This exception is raised by Load (75) method of TElfResourceReader (76) when version field of ELF header is not 1.

## 8.8 TElfResourceReader

### 8.8.1 Description

This class provides a reader for ELF object files and images containing resources.

ELF is the file format used by unices and other operating systems for object files and image files (executables, dynamic libraries and so on). Free Pascal can store resources in ELF files in its own format.

After an object file has been read, MachineType (77) property holds the machine type the object file was built for.

**Remark:** This reader can't read ELF files without section headers. These are however very rare.

See also: TElfResourceReader.MachineType (77), TAbstractResourceReader (75), TElfResourceWriter (75), Format of resources in object files (75)

### 8.8.2 Method overview

Page	Method	Description
77	CheckMagic	
77	Create	
77	Destroy	
77	GetDescription	
77	GetExtensions	
77	Load	

### 8.8.3 Property overview

Page	Properties	Access	Description
<a href="#">77</a>	MachineType	r	The machine type of the object file

### 8.8.4 TElfResourceReader.GetExtensions

Declaration: `function GetExtensions : string; Override`

Visibility: `protected`

### 8.8.5 TElfResourceReader.GetDescription

Declaration: `function GetDescription : string; Override`

Visibility: `protected`

### 8.8.6 TElfResourceReader.Load

Declaration: `procedure Load(aResources: TResources; aStream: TStream); Override`

Visibility: `protected`

### 8.8.7 TElfResourceReader.CheckMagic

Declaration: `function CheckMagic(aStream: TStream) : Boolean; Override`

Visibility: `protected`

### 8.8.8 TElfResourceReader.Create

Declaration: `constructor Create; Override`

Visibility: `public`

### 8.8.9 TElfResourceReader.Destroy

Declaration: `destructor Destroy; Override`

Visibility: `public`

### 8.8.10 TElfResourceReader.MachineType

Synopsis: The machine type of the object file

Declaration: `Property MachineType : TElfMachineType`

Visibility: `public`

Access: `Read`

Description: This property holds the machine type of the object file that has been read.

**Remark:** Obviously, this property is meaningful only after an object file has been read.

See also: `TElfMachineType` ([75](#))

## Chapter 9

# Reference for unit 'elfwriter'

### 9.1 Used units

Table 9.1: Used units by unit 'elfwriter'

Name	Page
Classes	??
elfconsts	<a href="#">69</a>
elftypes	??
resource	<a href="#">127</a>
System	??
sysutils	??

### 9.2 Overview

This unit contains `TElfResourceWriter` ([79](#)), a `TAbstractResourceWriter` ([78](#)) descendant that is able to write ELF object files containing resources.

Adding this unit to a program's `uses` clause registers class `TElfResourceWriter` ([79](#)) with `TResources` ([78](#)).

### 9.3 EElfResourceWriterException

#### 9.3.1 Description

Base class for elf resource writer-related exceptions

### 9.4 EElfResourceWriterUnknownClassException

#### 9.4.1 Description

If this exception is raised, an internal error occurred.

## 9.5 EElfResourceWriterUnknownMachineException

### 9.5.1 Description

This exception is raised when an attempt is made to set TElfResourceWriter.MachineType (80) to an unknown machine type.

See also: TElfResourceWriter.MachineType (80)

## 9.6 EElfResourceWriterUnknownSectionException

### 9.6.1 Description

If this exception is raised, an internal error occurred.

## 9.7 TElfResourceWriter

### 9.7.1 Description

This class provides a writer for ELF object files and images containing resources.

ELF is the file format used by unices and other operating systems for object files and image files (executables, dynamic libraries and so on). Free Pascal can store resources in ELF files in its own format.

MachineType (80) property can be used to set the machine type of the object file to generate.

See also: TElfResourceWriter.MachineType (80), TAbstractResourceWriter (78), TElfResourceReader (78), Format of resources in object files (78)

### 9.7.2 Method overview

Page	Method	Description
<a href="#">80</a>	Create	
<a href="#">80</a>	Destroy	
<a href="#">80</a>	GetDescription	
<a href="#">79</a>	GetExtensions	
<a href="#">80</a>	Write	

### 9.7.3 Property overview

Page	Properties	Access	Description
<a href="#">80</a>	MachineType	rw	The machine type of the object file

### 9.7.4 TElfResourceWriter.GetExtensions

Declaration: `function GetExtensions : string; Override`

Visibility: `protected`



### 9.7.5 TElfResourceWriter.GetDescription

Declaration: `function GetDescription : string; Override`

Visibility: `protected`

### 9.7.6 TElfResourceWriter.Write

Declaration: `procedure Write(aResources: TResources; aStream: TStream); Override`

Visibility: `protected`

### 9.7.7 TElfResourceWriter.Create

Declaration: `constructor Create; Override`

Visibility: `public`

### 9.7.8 TElfResourceWriter.Destroy

Declaration: `destructor Destroy; Override`

Visibility: `public`

### 9.7.9 TElfResourceWriter.MachineType

Synopsis: The machine type of the object file

Declaration: `Property MachineType : TElfMachineType`

Visibility: `public`

Access: `Read,Write`

Description: This property can be used to set the machine type of the object file to write.

If an attempt is made to set `MachineType` to an unsupported value, an `EElfResourceWriterUnknownMachineException` (79) exception is raised.

See also: `TElfMachineType` (78), `EElfResourceWriterUnknownMachineException` (79)

## Chapter 10

# Reference for unit 'externalreader'

### 10.1 Used units

Table 10.1: Used units by unit 'externalreader'

Name	Page
Classes	??
externaltypes	<a href="#">84</a>
resource	<a href="#">127</a>
resourcetree	<a href="#">162</a>
System	??
sysutils	??

### 10.2 Overview

This unit contains TExternalResourceReader ([81](#)), a TAbstractResourceReader ([81](#)) descendant that is able to read standalone resource files in a Free Pascal-specific format.

Adding this unit to a program's `uses` clause registers class TExternalResourceReader ([81](#)) with TResources ([81](#)).

#### See also

Free Pascal external resource file format description ([81](#))

### 10.3 TExternalResourceReader

#### 10.3.1 Description

This class provides a reader for .fpcres files: they are standalone files containing resources.

Standalone files are files that don't get linked with the final executable. They are used as a fallback solution on all those platforms for which an internal resource format is not available.

At runtime the resource file is read by Free Pascal RTL to provide resource support to the application.

After an external file has been read, Endianness ([83](#)) property holds the byte order used in the file.

See also: TExternalResourceReader.Endianess ([83](#)), TAbstractResourceReader ([81](#)), TExternalResourceWriter ([81](#))

### 10.3.2 Method overview

Page	Method	Description
<a href="#">82</a>	CheckMagic	
<a href="#">82</a>	Create	
<a href="#">82</a>	Destroy	
<a href="#">82</a>	GetDescription	
<a href="#">82</a>	GetExtensions	
<a href="#">82</a>	Load	

### 10.3.3 Property overview

Page	Properties	Access	Description
<a href="#">83</a>	Endianess	r	The byte order used in the file

### 10.3.4 TExternalResourceReader.GetExtensions

Declaration: `function GetExtensions : string; Override`

Visibility: `protected`

### 10.3.5 TExternalResourceReader.GetDescription

Declaration: `function GetDescription : string; Override`

Visibility: `protected`

### 10.3.6 TExternalResourceReader.Load

Declaration: `procedure Load(aResources: TResources; aStream: TStream); Override`

Visibility: `protected`

### 10.3.7 TExternalResourceReader.CheckMagic

Declaration: `function CheckMagic(aStream: TStream) : Boolean; Override`

Visibility: `protected`

### 10.3.8 TExternalResourceReader.Create

Declaration: `constructor Create; Override`

Visibility: `public`

### 10.3.9 TExternalResourceReader.Destroy

Declaration: `destructor Destroy; Override`

Visibility: `public`

### 10.3.10 TExternalResourceReader.Endianess

Synopsis: The byte order used in the file

Declaration: `Property Endianess : Byte`

Visibility: `public`

Access: `Read`

Description: This property holds the byte order (endianess) of the file that has been read.

**Remark:** Obviously, this property is meaningful only after a file has been read.

See also: `EXT_ENDIAN_BIG` ([81](#)), `EXT_ENDIAN_LITTLE` ([81](#))

# Chapter 11

## Reference for unit 'externaltypes'

### 11.1 Used units

Table 11.1: Used units by unit 'externaltypes'

Name	Page
System	??

### 11.2 Overview

These types are used internally by TExternalResourceReader (84) and TExternalResourceWriter (84).

Two constants are of interest: EXT\_ENDIAN\_BIG (87) and EXT\_ENDIAN\_LITTLE (87).

### 11.3 Description of external resource file format

#### Introduction

An external resource file (.fpcres extension) provides resource support for those systems where a resource format suitable to be embedded in an object file isn't available.

The file format is designed in a way similar to other internal resource formats. The file is opened at program startup and is mapped in the program address space. Offsets in the file are easily converted to pointers at runtime since those offsets represent a displacement from a base address (the starting address where the file is mapped). Differences from an internal file format hence lie in the fact that resources aren't mapped in the program address space by the program loader but by Free Pascal RTL, and data must be accessed with a displacement mechanism instead of absolute pointers.

For internal resources details, see Format of resources in object files (84)

#### File layout

An external resource file consists of these parts:

- The initial header, containing various file information
- The resource tree, in the form of nodes

- The string table, which can be optional
- The resource data

The header is made up by initial header, resource tree and string table (if present).

### Conventions

In this document, data sizes are specified with pascal-style data types. They are the following:

Table 11.2:

Name	Meaning
byte	Unsigned 8 bit integer.
longword	Unsigned 32 bit integer.
qword	Unsigned 64 bit integer.

Byte order used in the file is specified in the initial header.

All data structures in the file must be aligned on qword boundaries.

### The initial header

An external resource file starts with this header:

Table 11.3:

Name	Offset	Length	Description
magic	0	6	Six ASCII characters that form the string <code>FPCRES</code>
version	6	byte	File format version. Currently it is 1.
endianess	7	byte	Byte order. 1 for big endian, 2 for little endian
count	8	longword	Number of resources in the file
nodesize	12	longword	Size of header up to the string table, excluded
hdrsize	16	longword	Full size of header (up to the string table, included)
reserved	20	12	Must be zero

Note that byte order of the file can be read in the `endianess` field of the header. All data fields longer than a byte are written with the byte order specified in `endianess`.

If no resource name or type is identified by strings, string table is optional. When this is the case, `nodesize` and `hdrsize` have the same value.

### The resource tree

Immediately following the initial header, the resource tree comes. It is made up by nodes that represent resource types, names and language ids.

Data is organized so that resource information (type, name and language id) is represented by a tree: root node contains resource types, that in turn contain resource names, which contain language ids, which describe resource data.

Given a node, its sub-nodes are ordered as follows:

- First the "named" nodes (nodes that use a string as identifier) come, then the id ones (nodes that use an integer as identifier).
- Named nodes are alphabetically sorted, in ascending order.

- Id nodes are sorted in ascending order.

In the file, all sub-nodes of a node are written in the order described above. Then, all sub-nodes of the first sub-node are written, and so on.

**Example:**

There are three resources:

1. a BITMAP resource with name MYBITMAP and language id \$0409
2. a BITMAP resource with name 1 and language id 0
3. a resource with type MYTYPE and name 1 and language id 0

Nodes are laid out this way (note that BITMAP resources have type 2):

```
root | MYTYPE 2 | 1 | 0 | MYBITMAP 1 | $0409 | 0
```

That is, types (MYTYPE is a string, so it comes before 2 which is BITMAP), then names for MYTYPE (1), then language id for resource 3 (0), then names for BITMAP (MYBITMAP and 1), then language id for resource 1 (\$0409), then language id for resource 2 (0).

**Node format**

Table 11.4:

Name	Offset	Length	Description
nameid	0	longword	name offset, integer id or language id
ncount	4	longword	named sub-nodes count
idcountsize	8	longword	id sub-nodes count or resource size
subptr	12	longword	offset to first sub-node

Note that all offset are always relative to the beginning of the file.

If the node is identified by a string, `nameid` is an offset to the null-terminated string holding the name. If it is identified by an id, `nameid` is that id. Language id nodes are always identified by and ID.

`ncount` is the number of named sub-nodes of this node (nodes that are identified by a string).

`idcountsize` is the number of id sub-nodes of this node (nodes that are identified by an integer id). For language id nodes, this field holds the size of the resource data.

`subptr` is an offset to the first subnode of this node. Note that it allows to access every subnode of this node, since subnodes of a node always come one after the other. For language id nodes, `subptr` is the offset to the resource data.

**The string table**

The string table is used to store strings used for resource types and names. If all resources use integer ids for name and types, it may not be present in the file.

The string table simply contains null-terminated strings, one after the other.

If present, the string table always contains a 0 (zero) at the beginning. This way, the empty string is located at the offset of the string table (whose value is held in `nodesize` field of the initial header).

**The resource data**

This part of the file contains raw resource data. As written before, all data structures must be aligned on qword boundaries, so if a resource data size is not a multiple of 8, bytes of padding must be inserted after that resource data.

## 11.4 Constants, types and variables

### 11.4.1 Constants

```
EXTERNAL_RESMAGIC : TExternalResMagic = 'FPCRES'
```

This value is used for TExtHeader.magic (87).

```
EXT_CURRENT_VERSION = 1
```

This value is used for TExtHeader.version (87).

```
EXT_ENDIAN_BIG = 1
```

This value is used for TExtHeader.endianness (87).

```
EXT_ENDIAN_LITTLE = 2
```

This value is used for TExtHeader.endianness (87).

### 11.4.2 Types

```
TExternalResMagic = Array[1..6] of Char
```

Type used for the magic identifier in external resource files

```
TExtHeader = packed record
  magic : TExternalResMagic;
  version
  : Byte;
  endianness : Byte;
  count : LongWord;
  nodesize : LongWord
  ;
  hdrsize : LongWord;
  reserved1 : LongWord;
  reserved2 : LongWord
  ;
  reserved3 : LongWord;
end
```

This header describes the data structure present at the beginning of an external resource file.

```
TResInfoNode = packed record
  nameid : LongWord;
  ncount : LongWord
  ;
  idcountsize : LongWord;
  subptr : LongWord;
end
```

This record represents a node used in a resource tree. A node contains information about a certain resource type, name or language id.



## Chapter 12

# Reference for unit 'externalwriter'

### 12.1 Used units

Table 12.1: Used units by unit 'externalwriter'

Name	Page
Classes	??
externaltypes	<a href="#">84</a>
resource	<a href="#">127</a>
resourcetree	<a href="#">162</a>
strtable	??
System	??
sysutils	??

### 12.2 Overview

This unit contains TExternalResourceWriter ([89](#)), a TAbstractResourceWriter ([88](#)) descendant that is able to write standalone resource files in a Free Pascal-specific format.

Adding this unit to a program's `uses` clause registers class TExternalResourceWriter ([89](#)) with TResources ([88](#)).

#### See also

Free Pascal external resource file format description ([88](#))

### 12.3 EExternalResInvalidEndiannessException

#### 12.3.1 Description

This exception is raised when an attempt is made to set Endianness ([90](#)) property of a TExternalResourceWriter ([89](#)) object to a value other than EXT\_ENDIAN\_BIG ([88](#)) or EXT\_ENDIAN\_LITTLE ([88](#)).

See also: TExternalResourceWriter.Endianness ([90](#))

## 12.4 EExternalResourceWriterException

### 12.4.1 Description

Base class for external resource writer-related exceptions

## 12.5 TExternalResourceWriter

### 12.5.1 Description

This class provides a writer for .fpcres files: they are standalone files containing resources.

Standalone files are files that don't get linked with the final executable. They are used as a fallback solution on all those platforms for which an internal resource format is not available.

At runtime the resource file is read by Free Pascal RTL to provide resource support to the application.

Endianness (90) property can be used to set the byte order to use in the file to generate.

See also: TExternalResourceWriter.Endianness (90), TAbstractResourceWriter (88), TExternalResourceReader (88)

### 12.5.2 Method overview

Page	Method	Description
<a href="#">90</a>	Create	
<a href="#">90</a>	Destroy	
<a href="#">89</a>	GetDescription	
<a href="#">89</a>	GetExtensions	
<a href="#">89</a>	Write	

### 12.5.3 Property overview

Page	Properties	Access	Description
<a href="#">90</a>	Endianness	rw	The byte order to use in the file

### 12.5.4 TExternalResourceWriter.GetExtensions

Declaration: `function GetExtensions : string; Override`

Visibility: protected

### 12.5.5 TExternalResourceWriter.GetDescription

Declaration: `function GetDescription : string; Override`

Visibility: protected

### 12.5.6 TExternalResourceWriter.Write

Declaration: `procedure Write(aResources: TResources; aStream: TStream); Override`

Visibility: protected

### 12.5.7 TExternalResourceWriter.Create

Declaration: constructor Create; Override

Visibility: public

### 12.5.8 TExternalResourceWriter.Destroy

Declaration: destructor Destroy; Override

Visibility: public

### 12.5.9 TExternalResourceWriter.Endianess

Synopsis: The byte order to use in the file

Declaration: Property Endianess : Byte

Visibility: public

Access: Read,Write

Description: This property can be used to set the byte order (endianess) of the file to write.

**Remark:** If a value other than EXT\_ENDIAN\_BIG (88) or EXT\_ENDIAN\_LITTLE (88) is used, an EExternalResInvalidEndianessException (88) exception is raised.

See also: EXT\_ENDIAN\_BIG (88), EXT\_ENDIAN\_LITTLE (88)

## Chapter 13

# Reference for unit 'groupcursorresource'

### 13.1 Used units

Table 13.1: Used units by unit 'groupcursorresource'

Name	Page
Classes	??
groupresource	<a href="#">99</a>
resource	<a href="#">127</a>
System	??
sysutils	??

### 13.2 Overview

This unit contains `TGroupCursorResource` ([91](#)), a `TAbstractResource` ([91](#)) descendant specialized in handling resource of type `RT_GROUP_CURSOR` ([91](#)).

Adding this unit to a program's `uses` clause registers class `TGroupCursorResource` ([91](#)) for type `RT_GROUP_CURSOR` ([91](#)) with `TResourceFactory` ([91](#)).

### 13.3 TGroupCursorResource

#### 13.3.1 Description

This class represents a resource of type `RT_GROUP_CURSOR` ([91](#)).

Resources of this type are strictly related to `.cur` files: typically a resource compiler creates resources of this type when it is instructed to insert a cursor from a `.cur` file.

There is although a big difference between `.cur` files and cursor resources: a `.cur` file contains a cursor, which is made of several different images (for different sizes and color depth), but while a file of this type is self-contained, when it comes to resources data is scattered over several different resources: an `RT_GROUP_CURSOR` ([91](#)) resource only contains information about the single images, which are contained each in a different resource of type `RT_CURSOR` ([91](#)). The single resources are pretty

unuseful alone, since they only consist of raw image data: they must be accessed in the contest of the `RT_GROUP_CURSOR` (91) resource, which provides information about them.

`TGroupCursorResource` (91) provides a way to handle a cursor as if it was a .cur file, via `ItemData` (91) property. Single cursor resources are automatically created or destroyed as needed.

**Remark:** This class doesn't allow its type to be changed to anything else than `RT_GROUP_CURSOR` (91). Attempts to do so result in a `EResourceDescChangeNotAllowedException` (91).

See also: `TGroupResource.ItemData` (91), `TGroupIconResource` (91)

### 13.3.2 Method overview

Page	Method	Description
93	<code>ChangeDescTypeAllowed</code>	
93	<code>ChangeDescValueAllowed</code>	
93	<code>ClearItemList</code>	
93	<code>Create</code>	Creates a new group cursor resource
92	<code>CreateSubItem</code>	
93	<code>DeleteSubItems</code>	
93	<code>GetName</code>	
93	<code>GetSubStream</code>	
93	<code>GetType</code>	
92	<code>ReadResourceItemHeader</code>	
92	<code>UpdateItemOwner</code>	
92	<code>WriteHeader</code>	

### 13.3.3 TGroupCursorResource.ReadResourceItemHeader

Declaration: `procedure ReadResourceItemHeader; Override`

Visibility: `protected`

### 13.3.4 TGroupCursorResource.WriteHeader

Declaration: `procedure WriteHeader(aStream: TStream); Override`

Visibility: `protected`

### 13.3.5 TGroupCursorResource.CreateSubItem

Declaration: `procedure CreateSubItem; Override`

Visibility: `protected`

### 13.3.6 TGroupCursorResource.UpdateItemOwner

Declaration: `procedure UpdateItemOwner(index: Integer); Override`

Visibility: `protected`

### 13.3.7 TGroupCursorResource.ClearItemList

Declaration: `procedure ClearItemList; Override`

Visibility: `protected`

### 13.3.8 TGroupCursorResource.DeleteSubItems

Declaration: `procedure DeleteSubItems; Override`

Visibility: `protected`

### 13.3.9 TGroupCursorResource.GetSubStream

Declaration: `function GetSubStream(const index: Integer; out aSize: Int64) : TStream  
; Override`

Visibility: `protected`

### 13.3.10 TGroupCursorResource.GetType

Declaration: `function GetType : TResourceDesc; Override`

Visibility: `protected`

### 13.3.11 TGroupCursorResource.GetName

Declaration: `function GetName : TResourceDesc; Override`

Visibility: `protected`

### 13.3.12 TGroupCursorResource.ChangeDescTypeAllowed

Declaration: `function ChangeDescTypeAllowed(aDesc: TResourceDesc) : Boolean  
; Override`

Visibility: `protected`

### 13.3.13 TGroupCursorResource.ChangeDescValueAllowed

Declaration: `function ChangeDescValueAllowed(aDesc: TResourceDesc) : Boolean  
; Override`

Visibility: `protected`

### 13.3.14 TGroupCursorResource.Create

Synopsis: Creates a new group cursor resource

Declaration: `constructor Create; Override  
constructor Create(aType: TResourceDesc; aName: TResourceDesc)  
; Override`

Visibility: `public`

Description: Please note that `aType` parameter is not used, since this class always uses `RT_GROUP_CURSOR` (91) as type.

## Chapter 14

# Reference for unit 'groupiconresource'

### 14.1 Used units

Table 14.1: Used units by unit 'groupiconresource'

Name	Page
Classes	??
groupresource	<a href="#">99</a>
resource	<a href="#">127</a>
System	??
sysutils	??

### 14.2 Overview

This unit contains `TGroupIconResource` ([95](#)), a `TAbstractResource` ([95](#)) descendant specialized in handling resource of type `RT_GROUP_ICON` ([95](#)).

Adding this unit to a program's `uses` clause registers class `TGroupIconResource` ([95](#)) for type `RT_GROUP_ICON` ([95](#)) with `TResourceFactory` ([95](#)).

### 14.3 TGroupIconResource

#### 14.3.1 Description

This class represents a resource of type `RT_GROUP_ICON` ([95](#)).

Resources of this type are strictly related to `.ico` files: typically a resource compiler creates resources of this type when it is instructed to insert an icon from an `.ico` file.

There is although a big difference between `.ico` files and icon resources: an `.ico` file contains an icon, which is made of several different images (for different sizes and color depth), but while a file of this type is self-contained, when it comes to resources data is scattered over several different resources: an `RT_GROUP_ICON` ([95](#)) resource only contains information about the single images, which are contained each in a different resource of type `RT_ICON` ([95](#)). The single resources are



pretty useless alone, since they only consist of raw image data: they must be accessed in the context of the RT\_GROUP\_ICON (95) resource, which provides information about them.

TGroupIconResource (95) provides a way to handle an icon as if it was a .ico file, via ItemData (95) property. Single icon resources are automatically created or destroyed as needed.

**Remark:** This class doesn't allow its type to be changed to anything else than RT\_GROUP\_ICON (95). Attempts to do so result in a EResourceDescChangeNotAllowedException (95).

See also: TGroupResource.ItemData (95), TGroupCursorResource (95)

### 14.3.2 Method overview

Page	Method	Description
97	ChangeDescTypeAllowed	Creates a new group icon resource
97	ChangeDescValueAllowed	
97	ClearItemList	
97	Create	
96	CreateSubItem	
97	DeleteSubItems	
97	GetName	
97	GetSubStream	
97	GetType	
96	ReadResourceItemHeader	
96	UpdateItemOwner	
96	WriteHeader	

### 14.3.3 TGroupIconResource.ReadResourceItemHeader

Declaration: procedure ReadResourceItemHeader; Override

Visibility: protected

### 14.3.4 TGroupIconResource.WriteHeader

Declaration: procedure WriteHeader(aStream: TStream); Override

Visibility: protected

### 14.3.5 TGroupIconResource.CreateSubItem

Declaration: procedure CreateSubItem; Override

Visibility: protected

### 14.3.6 TGroupIconResource.UpdateItemOwner

Declaration: procedure UpdateItemOwner(index: Integer); Override

Visibility: protected

### 14.3.7 TGroupIconResource.ClearItemList

Declaration: `procedure ClearItemList; Override`

Visibility: `protected`

### 14.3.8 TGroupIconResource.DeleteSubItems

Declaration: `procedure DeleteSubItems; Override`

Visibility: `protected`

### 14.3.9 TGroupIconResource.GetSubStream

Declaration: `function GetSubStream(const index: Integer; out aSize: Int64) : TStream  
; Override`

Visibility: `protected`

### 14.3.10 TGroupIconResource.GetType

Declaration: `function GetType : TResourceDesc; Override`

Visibility: `protected`

### 14.3.11 TGroupIconResource.GetName

Declaration: `function GetName : TResourceDesc; Override`

Visibility: `protected`

### 14.3.12 TGroupIconResource.ChangeDescTypeAllowed

Declaration: `function ChangeDescTypeAllowed(aDesc: TResourceDesc) : Boolean  
; Override`

Visibility: `protected`

### 14.3.13 TGroupIconResource.ChangeDescValueAllowed

Declaration: `function ChangeDescValueAllowed(aDesc: TResourceDesc) : Boolean  
; Override`

Visibility: `protected`

### 14.3.14 TGroupIconResource.Create

Synopsis: Creates a new group icon resource

Declaration: `constructor Create; Override  
constructor Create(aType: TResourceDesc; aName: TResourceDesc)  
; Override`

Visibility: `public`

**Description:** Please note that `aType` parameter is not used, since this class always uses `RT_GROUP_ICON` (95) as type.

## Chapter 15

# Reference for unit 'groupresource'

### 15.1 Used units

Table 15.1: Used units by unit 'groupresource'

Name	Page
Classes	??
resdatastream	<a href="#">117</a>
resource	<a href="#">127</a>
System	??
sysutils	??

### 15.2 Overview

This unit contains [TGroupResource \(100\)](#) and [TGroupCachedDataStream \(99\)](#), two classes used for resources of type [RT\\_GROUP\\_ICON \(99\)](#) and [RT\\_GROUP\\_CURSOR \(99\)](#).

The former is an abstract resource class which is implemented by [TGroupIconResource \(99\)](#) and [TGroupCursorResource \(99\)](#), and the latter is a [TCachedDataStream \(99\)](#) descendant used to provide .ico/.cur like streams for resource classes mentioned earlier.

This unit shouldn't be of interest for the user, who should look at documentation for [groupiconresource \(99\)](#) and [groupcursorresource \(99\)](#) units instead.

### 15.3 TGroupCachedDataStream

#### 15.3.1 Description

This class is used by [TGroupResource \(100\)](#) descendants to provide an .ico/.cur like stream.

Unlike [TCachedResourceDataStream \(99\)](#), which provides a stream-like interface over a portion of another stream, this class lets multiple stream to be seen as one: this way, several [RT\\_ICON \(99\)](#) or [RT\\_CURSOR \(99\)](#) resources can appear like a single .ico or .cur file.

See also: [TGroupResource \(100\)](#), [TGroupIconResource \(99\)](#), [TGroupCursorResource \(99\)](#), [TCachedDataStream \(99\)](#), [TCachedResourceDataStream \(99\)](#)

### 15.3.2 Method overview

Page	Method	Description
<a href="#">100</a>	Create	
<a href="#">100</a>	Destroy	
<a href="#">100</a>	Read	

### 15.3.3 TGroupCachedDataStream.Create

Declaration: `constructor Create(aStream: TStream; aResource: TAbstractResource; aSize: Int64); Override`

Visibility: public

### 15.3.4 TGroupCachedDataStream.Destroy

Declaration: `destructor Destroy; Override`

Visibility: public

### 15.3.5 TGroupCachedDataStream.Read

Declaration: `function Read(var Buffer; Count: LongInt) : LongInt; Override`

Visibility: public

## 15.4 TGroupResource

### 15.4.1 Description

This class provides common functionalities that are extended by [TGroupIconResource \(99\)](#) and [TGroupCursorResource \(99\)](#).

Resources of type [RT\\_GROUP\\_ICON \(99\)](#) and [RT\\_GROUP\\_CURSOR \(99\)](#) represent a .ico or .cur file, respectively. However, data isn't contained in a single resource, but it's scattered over several different resources. That is, a .ico file contains an icon, which is made of several different images (for different sizes and color depth); when it is represented as a resource, however, the [RT\\_GROUP\\_ICON \(99\)](#) resource only contains information about the single images, which are contained each in a different resource of type [RT\\_ICON \(99\)](#). The single resources are pretty unuseful alone, since they only consist of raw image data: they must be accessed in the context of the [RT\\_GROUP\\_ICON \(99\)](#) resource, which provides information about them.

[TGroupIconResource \(99\)](#) and [TGroupCursorResource \(99\)](#) provide a way to handle resources of these types as if they were .ico or .cur files. This class implements common functionalities, since icons and cursors are very similar.

**Remark:** An object of this class should never be directly instantiated: use a descendant class instead.

See also: [TGroupIconResource \(99\)](#), [TGroupCursorResource \(99\)](#)

**15.4.2 Method overview**

Page	Method	Description
<a href="#">101</a>	CheckBuildItemStream	
<a href="#">102</a>	ClearItemList	
<a href="#">103</a>	CompareContents	
<a href="#">102</a>	CreateSubItem	
<a href="#">102</a>	CreateSubItems	
<a href="#">102</a>	DeleteSubItems	
<a href="#">103</a>	Destroy	
<a href="#">101</a>	FindSubResources	
<a href="#">101</a>	GetItemData	
<a href="#">102</a>	GetSubStream	
<a href="#">102</a>	GetSubStreamCount	
<a href="#">103</a>	NotifyResourcesLoaded	
<a href="#">101</a>	ReadResourceItemHeader	
<a href="#">103</a>	SetCustomItemDataStream	Sets a custom stream as the underlying stream for ItemData
<a href="#">103</a>	SetOwnerList	
<a href="#">102</a>	UpdateItemOwner	
<a href="#">104</a>	UpdateRawData	
<a href="#">102</a>	WriteHeader	
<a href="#">102</a>	WriteResHeader	

**15.4.3 Property overview**

Page	Properties	Access	Description
<a href="#">104</a>	ItemData	r	Resource data as an ICO/CUR stream

**15.4.4 TGroupResource.FindSubResources**

Declaration: `procedure FindSubResources`

Visibility: `protected`

**15.4.5 TGroupResource.ReadResourceItemHeader**

Declaration: `procedure ReadResourceItemHeader; Virtual; Abstract`

Visibility: `protected`

**15.4.6 TGroupResource.CheckBuildItemStream**

Declaration: `procedure CheckBuildItemStream`

Visibility: `protected`

**15.4.7 TGroupResource.GetItemData**

Declaration: `function GetItemData : TStream`

Visibility: `protected`

#### **15.4.8 TGroupResource.WriteHeader**

Declaration: procedure WriteHeader(aStream: TStream); Virtual; Abstract

Visibility: protected

#### **15.4.9 TGroupResource.WriteResHeader**

Declaration: function WriteResHeader : Word

Visibility: protected

#### **15.4.10 TGroupResource.CreateSubItems**

Declaration: procedure CreateSubItems

Visibility: protected

#### **15.4.11 TGroupResource.CreateSubItem**

Declaration: procedure CreateSubItem; Virtual; Abstract

Visibility: protected

#### **15.4.12 TGroupResource.UpdateItemOwner**

Declaration: procedure UpdateItemOwner(index: Integer); Virtual; Abstract

Visibility: protected

#### **15.4.13 TGroupResource.ClearItemList**

Declaration: procedure ClearItemList; Virtual; Abstract

Visibility: protected

#### **15.4.14 TGroupResource.DeleteSubItems**

Declaration: procedure DeleteSubItems; Virtual; Abstract

Visibility: protected

#### **15.4.15 TGroupResource.GetSubStreamCount**

Declaration: function GetSubStreamCount : Integer

Visibility: protected

#### **15.4.16 TGroupResource.GetSubStream**

Declaration: function GetSubStream(const index: Integer; out aSize: Int64) : TStream  
; Virtual; Abstract

Visibility: protected

### 15.4.17 TGroupResource.SetOwnerList

Declaration: `procedure SetOwnerList(aResources: TResources); Override`

Visibility: `protected`

### 15.4.18 TGroupResource.NotifyResourcesLoaded

Declaration: `procedure NotifyResourcesLoaded; Override`

Visibility: `protected`

### 15.4.19 TGroupResource.Destroy

Synopsis:

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description:

### 15.4.20 TGroupResource.CompareContents

Declaration: `function CompareContents(aResource: TAbstractResource) : Boolean  
; Override`

Visibility: `public`

### 15.4.21 TGroupResource.SetCustomItemDataStream

Synopsis: Sets a custom stream as the underlying stream for ItemData

Declaration: `procedure SetCustomItemDataStream(aStream: TStream)`

Visibility: `public`

Description: This method allows the user to use a custom stream as the underlying stream for ItemData (104). This is useful when you want a TGroupIconResource (99) or TGroupCursorResource (99) to be created from a ico or cur file for which you have a stream.

#### Sample code

This code creates a resource containing an icon

```
var
  aName : TResourceDesc;
  aRes : TGroupIconResource;
  aFile : TFileStream;
  Resources : TResources;
begin
  Resources:=TResources.Create;
  aName:=TResourceDesc.Create('MAINICON');
  aRes:=TGroupIconResource.Create(nil,aName); //type is always RT_GROUP_ICON
  aName.Free; //not needed anymore
  aFile:=TFileStream.Create('mainicon.ico',fmOpenRead or fmShareDenyNone);
```



```

aRes.SetCustomItemDataStream(aFile);
Resources.Add(aRes);
Resources.WriteToFile('myresource.res');

Resources.Free; //it destroys aRes as well.
aFile.Free;
end;

```

See also: [TGroupResource.ItemData \(104\)](#), [TGroupIconResource \(99\)](#), [TGroupCursorResource \(99\)](#), [TAbstractResource.UpdateRawData \(99\)](#)

### 15.4.22 TGroupResource.UpdateRawData

Declaration: `procedure UpdateRawData; Override`

Visibility: `public`

### 15.4.23 TGroupResource.ItemData

Synopsis: Resource data as an ICO/CUR stream

Declaration: `Property ItemData : TStream`

Visibility: `public`

Access: `Read`

Description: This property gives access to resource data in a (ICO or CUR) file-like stream, unlike [RawData \(99\)](#).

The exact format of the stream (ico or cur) is determined by the descendant class of [TGroupResource \(100\)](#) that is used.

[ItemData](#) does not create a copy of [RawData \(99\)](#) so memory usage is generally kept limited.

You can also set a custom stream as the underlying stream for [ItemData](#) via [SetCustomItemDataStream \(103\)](#), much like [SetCustomRawDataStream \(99\)](#) does for [RawData \(99\)](#). This is useful when you want a [TGroupIconResource \(99\)](#) or [TGroupCursorResource \(99\)](#) to be created from a ico or cur file for which you have a stream.

**Remark:** If you need to access [RawData \(99\)](#) after you modified [ItemData](#), be sure to call [UpdateRawData \(99\)](#) first. This isn't needed however when resource is written to a stream, since [TResources \(99\)](#) takes care of it.

See also: [TGroupResource.SetCustomItemDataStream \(103\)](#), [TGroupIconResource \(99\)](#), [TGroupCursorResource \(99\)](#), [TAbstractResource.RawData \(99\)](#), [TAbstractResource.UpdateRawData \(99\)](#)

## Chapter 16

# Reference for unit 'machoreader'

### 16.1 Used units

Table 16.1: Used units by unit 'machoreader'

Name	Page
Classes	??
machotypes	<a href="#">108</a>
resource	<a href="#">127</a>
System	??
sysutils	??

### 16.2 Overview

This unit contains `TMachOResourceReader` ([105](#)), a `TAbstractResourceReader` ([105](#)) descendant that is able to read Mach-O object files containing resources.

Adding this unit to a program's `uses` clause registers class `TMachOResourceReader` ([105](#)) with `TResources` ([105](#)).

### 16.3 TMachOResourceReader

#### 16.3.1 Description

This class provides a reader for Mach-O object files and images containing resources.

Mach-O is the file format used by Darwin and Mac OS X for object files and image files (executables, dynamic libraries and so on). Free Pascal can store resources in Mach-O files in its own format.

After an object file has been read, `MachineType` ([107](#)) property holds the machine type the object file was built for.

**Remark:** This reader can't read multiple-architecture Mach-O files (like universal binary). To read a particular Mach-O file in a multiple-architecture file, extract it with `lipo` command.

See also: `TMachOResourceReader.MachineType` ([107](#)), `TAbstractResourceReader` ([105](#)), `TMachOResourceWriter` ([105](#)), `Format of resources in object files` ([105](#))

### 16.3.2 Method overview

Page	Method	Description
<a href="#">106</a>	CheckMagic	
<a href="#">106</a>	Create	
<a href="#">106</a>	Destroy	
<a href="#">106</a>	GetDescription	
<a href="#">106</a>	GetExtensions	
<a href="#">106</a>	Load	

### 16.3.3 Property overview

Page	Properties	Access	Description
<a href="#">107</a>	MachineType	r	The machine type of the object file

### 16.3.4 TMachOResourceReader.GetExtensions

Declaration: `function GetExtensions : string; Override`

Visibility: `protected`

### 16.3.5 TMachOResourceReader.GetDescription

Declaration: `function GetDescription : string; Override`

Visibility: `protected`

### 16.3.6 TMachOResourceReader.Load

Declaration: `procedure Load(aResources: TResources; aStream: TStream); Override`

Visibility: `protected`

### 16.3.7 TMachOResourceReader.CheckMagic

Declaration: `function CheckMagic(aStream: TStream) : Boolean; Override`

Visibility: `protected`

### 16.3.8 TMachOResourceReader.Create

Declaration: `constructor Create; Override`

Visibility: `public`

### 16.3.9 TMachOResourceReader.Destroy

Declaration: `destructor Destroy; Override`

Visibility: `public`

### 16.3.10 **TMachOResourceReader.MachineType**

Synopsis: The machine type of the object file

Declaration: `Property MachineType : TMachOMachineType`

Visibility: `public`

Access: `Read`

Description: This property holds the machine type of the object file that has been read.

**Remark:** Obviously, this property is meaningful only after an object file has been read.

See also: `TMachOMachineType` ([105](#))

# Chapter 17

## Reference for unit 'machotypes'

### 17.1 Used units

Table 17.1: Used units by unit 'machotypes'

Name	Page
System	??

### 17.2 Overview

These constants are used internally by TMachOResourceWriter ([108](#)) and TMachOResourceReader ([108](#)).

The only type of interest for the user is TMachOMachineType ([109](#)).

### 17.3 Constants, types and variables

#### 17.3.1 Types

```
PNList32 = ^TNList32
```

```
PNList64 = ^TNList64
```

```
PRelocationInfo = ^TRelocationInfo
```

```
TDySymtabCommand = packed record
    ilocalsym : LongWord;
    nlocalsym
    : LongWord;
    iextdefsym : LongWord;
    nextdefsym : LongWord;
    iundefsym
```

```

: LongWord;
nundefsym : LongWord;
tocoff : LongWord;
ntoc
: LongWord;
modtaboff : LongWord;
nmodtab : LongWord;
extrefsymoff
: LongWord;
nextrefsyms : LongWord;
indirectsymoff : LongWord
;
nindirectsyms : LongWord;
extreloff : LongWord;
nextrel :
LongWord;
locreloff : LongWord;
nlocrel : LongWord;
end

```

```

TLoadCommand = packed record
  cmd : LongWord;
  cmdsize : LongWord
;
end

```

```

TMachHdr = packed record
  magic : LongWord;
  cputype : LongInt;
  cpusubtype : LongInt;
  filetype : LongWord;
  ncmds : LongWord
;
  sizeofcmds : LongWord;
  flags : LongWord;
end

```

```

TMachOMachineType = (mmtpowerpc, mmtpowerpc64, mmti386, mmtx86_64, mmtarm
)

```

Table 17.2: Enumeration values for type TMachOMachineType

Value	Explanation
mmtarm	
mmti386	Intel 386 machine type
mmtpowerpc	PowerPC machine type
mmtpowerpc64	PowerPC 64 machine type
mmtx86_64	AMD x86_64 machine type

This enumeration specifies the Mach-O machine type.

It is used by `TMachOResourceWriter` (108) to specify the machine type of the generated object file and by `TMachOResourceReader` (108) to read the machine type of the object file that has been read.

```
TMachOSubMachineType386 = (msm386_all)
```

Table 17.3: Enumeration values for type `TMachOSubMachineType386`

Value	Explanation
<code>msm386_all</code>	

```
TMachOSubMachineTypeArm = (msmarm_all, msmarm_v4t, msmarm_v6, msmarm_v5tej,
    ,
    msmarm_xscale, msmarm_v7)
```

Table 17.4: Enumeration values for type `TMachOSubMachineTypeArm`

Value	Explanation
<code>msmarm_all</code>	
<code>msmarm_v4t</code>	
<code>msmarm_v5tej</code>	
<code>msmarm_v6</code>	
<code>msmarm_v7</code>	
<code>msmarm_xscale</code>	

```
TMachOSubMachineTypePowerPC = (msmppc_all)
```

Table 17.5: Enumeration values for type `TMachOSubMachineTypePowerPC`

Value	Explanation
<code>msmppc_all</code>	

```
TMachOSubMachineTypePowerPC64 = (msmppc64_all)
```

Table 17.6: Enumeration values for type `TMachOSubMachineTypePowerPC64`

Value	Explanation
<code>msmppc64_all</code>	

```
TMachOSubMachineTypex64 = (msmx64_all)
```

Table 17.7: Enumeration values for type `TMachOSubMachineTypex64`

Value	Explanation
<code>msmx64_all</code>	

```
TNList32 = packed record
  strx : LongWord;
  _type : Byte;
  sect
    : Byte;
  desc : Word;
  value : LongWord;
end
```

```
TNList64 = packed record
  strx : LongWord;
  _type : Byte;
  sect
    : Byte;
  desc : Word;
  value : QWord;
end
```

```
TRelocationInfo = packed record
  address : LongWord;
  flags : LongWord
;
end
```

```
TSection32 = packed record
  sectname : TSegSectName;
  segname :
    TSegSectName;
  addr : LongWord;
  size : LongWord;
  offset : LongWord
;
  align : LongWord;
  reloff : LongWord;
  nreloc : LongWord;
  flags : LongWord;
  reserved1 : LongWord;
  reserved2 : LongWord
;
end
```

```
TSection64 = packed record
  sectname : TSegSectName;
  segname :
    TSegSectName;
  addr : QWord;
  size : QWord;
  offset : LongWord
;
  align : LongWord;
```



```

    reloff : LongWord;
    nreloc : LongWord;
    flags : LongWord;
    reserved1 : LongWord;
    reserved2 : LongWord
;
    reserved3 : LongWord;
end

```

```

TSegmentCommand32 = packed record
    name : TSegSectName;
    vmaddr
    : LongWord;
    vmsize : LongWord;
    fileoff : LongWord;
    filesize
    : LongWord;
    maxprot : LongInt;
    initprot : LongInt;
    nsects
    : LongWord;
    flags : LongWord;
end

```

```

TSegmentCommand64 = packed record
    name : TSegSectName;
    vmaddr
    : QWord;
    vmsize : QWord;
    fileoff : QWord;
    filesize : QWord
;
    maxprot : LongInt;
    initprot : LongInt;
    nsects : LongWord;
    flags : LongWord;
end

```

```

TSegSectName = Array[0..15] of Char

```

```

TSymtabCommand = packed record
    symoff : LongWord;
    nsyms : LongWord
;
    stroff : LongWord;
    strsize : LongWord;
end

```

## Chapter 18

# Reference for unit 'machowriter'

### 18.1 Used units

Table 18.1: Used units by unit 'machowriter'

Name	Page
Classes	??
machotypes	<a href="#">108</a>
resource	<a href="#">127</a>
System	??
sysutils	??

### 18.2 Overview

This unit contains `TMachOResourceWriter` ([114](#)), a `TAbstractResourceWriter` ([113](#)) descendant that is able to write Mach-O object files containing resources.

Adding this unit to a program's `uses` clause registers class `TMachOResourceWriter` ([114](#)) with `TResources` ([113](#)).

### 18.3 Constants, types and variables

#### 18.3.1 Types

```
TMachoSubMachineType = record
case TMachOMachineType of
msmppc_all
    : (
        fPpcSubType : TMachOSubMachineTypePowerPC;
    );
msmppc64_all:
    (
        fPpc64SubType : TMachOSubMachineTypePowerPC64;
    );
msm386_all
```

```

    : (
      f386SubType : TMachOSubMachineType386;
    );
    msxm64_all: (
      fX64SubType
        : TMachOSubMachineTypex64;
    );
    mmtarm: (
      fArmSubType : TMachOSubMachineTypeArm
    );
  end

```

## 18.4 EMachOResourceWriterException

### 18.4.1 Description

Base class for Mach-O resource writer-related exceptions

## 18.5 EMachOResourceWriterUnknownBitSizeException

### 18.5.1 Description

If this exception is raised, an internal error occurred.

## 18.6 TMachOResourceWriter

### 18.6.1 Description

This class provides a writer for Mach-O object files and images containing resources.

Mach-O is the file format used by Darwin and Mac OS X for object files and image files (executables, dynamic libraries and so on). Free Pascal can store resources in Mach-O files in its own format.

MachineType ([115](#)) property can be used to set the machine type of the object file to generate.

See also: TMachOResourceWriter.MachineType ([115](#)), TAbstractResourceWriter ([113](#)), TMachOResourceReader ([113](#)), Format of resources in object files ([113](#))

### 18.6.2 Method overview

Page	Method	Description
<a href="#">115</a>	Create	
<a href="#">115</a>	Destroy	
<a href="#">115</a>	GetDescription	
<a href="#">115</a>	GetExtensions	
<a href="#">115</a>	Write	

### 18.6.3 Property overview

Page	Properties	Access	Description
<a href="#">115</a>	MachineType	rw	The machine type of the object file
<a href="#">116</a>	SubMachineType	rw	

### 18.6.4 TMachOResourceWriter.GetExtensions

Declaration: `function GetExtensions : string; Override`

Visibility: `protected`

### 18.6.5 TMachOResourceWriter.GetDescription

Declaration: `function GetDescription : string; Override`

Visibility: `protected`

### 18.6.6 TMachOResourceWriter.Write

Declaration: `procedure Write(aResources: TResources; aStream: TStream); Override`

Visibility: `protected`

### 18.6.7 TMachOResourceWriter.Create

Declaration: `constructor Create; Override`

Visibility: `public`

### 18.6.8 TMachOResourceWriter.Destroy

Declaration: `destructor Destroy; Override`

Visibility: `public`

### 18.6.9 TMachOResourceWriter.MachineType

Synopsis: The machine type of the object file

Declaration: `Property MachineType : TMachOMachineType`

Visibility: `public`

Access: `Read,Write`

Description: This property can be used to set the machine type of the object file to write.

See also: `TMachOMachineType` ([113](#))

### 18.6.10 **TMachOResourceWriter.SubMachineType**

Declaration: `Property SubMachineType : TMachoSubMachineType`

Visibility: `public`

Access: `Read,Write`

## Chapter 19

# Reference for unit 'resdatastream'

### 19.1 Used units

Table 19.1: Used units by unit 'resdatastream'

Name	Page
Classes	??
resource	<a href="#">127</a>
System	??
sysutils	??

### 19.2 Overview

This unit contains various streams that are used to provide copy-on-write mechanism for TAbstractResource.RawData ([117](#)), via more levels of indirection.

Main class is TResourceDataStream ([120](#)), which is the stream used for TAbstractResource.RawData ([117](#)). This class uses an underlying stream, to which it redirects operations.

At a lower level, a TCachedDataStream ([118](#)) descendant provides a layer between the original stream and the TResourceDataStream ([120](#)).

### 19.3 Constants, types and variables

#### 19.3.1 Types

```
TCachedStreamClass = Class of TCachedDataStream
```

Cached stream metaclass

```
TUnderlyingStreamType = (usCached, usMemory, usCustom)
```

Table 19.2: Enumeration values for type TUnderlyingStreamType

Value	Explanation
usCached	The underlying stream is a TCachedResourceDataStream descendant
usCustom	The underlying stream is a custom stream
usMemory	The underlying stream is a memory stream

The type of the underlying stream of TResourceDataStream

## 19.4 TCachedDataStream

### 19.4.1 Description

This abstract class provides basic cached stream functionalities.

A cached stream is a read-only stream that operates on a portion of another stream. That is, it creates a "window" on the original stream from which to read data. Since it is a read-only stream, trying to write to the stream or to set its size cause an EInvalidOperation exception to be raised.

This class is used by TResourceDataStream (120) to access the raw data of a resource. When an attempt to write to the stream is detected, TResourceDataStream (120) replaces it with a memory stream and copies the contents of the cached stream to the memory one, thus providing a copy-on-write mechanism.

**Remark:** An object of this class should never be directly instantiated: use a descendant class instead.

See also: TResourceDataStream (120), TCachedResourceDataStream (119)

### 19.4.2 Method overview

Page	Method	Description
119	Create	Creates a new object
118	GetPosition	
119	GetSize	
119	Seek	
118	SetPosition	
119	SetSize64	
119	Write	

### 19.4.3 TCachedDataStream.GetPosition

Declaration: `function GetPosition : Int64; Override`

Visibility: protected

### 19.4.4 TCachedDataStream.SetPosition

Declaration: `procedure SetPosition(const Pos: Int64); Override`

Visibility: protected

### 19.4.5 TCachedDataStream.GetSize

Declaration: `function GetSize : Int64; Override`

Visibility: `protected`

### 19.4.6 TCachedDataStream.SetSize64

Declaration: `procedure SetSize64(const NewSize: Int64); Override`

Visibility: `protected`

### 19.4.7 TCachedDataStream.Create

Synopsis: Creates a new object

Declaration: `constructor Create(aStream: TStream; aResource: TAbstractResource;  
aSize: Int64); Virtual`

Visibility: `public`

Description: A new cached stream is created on top of the `aStream` stream.

See also: [TCachedDataStream \(118\)](#), [TResourceDataStream \(120\)](#), [TResourceDataStream.Create \(121\)](#)

### 19.4.8 TCachedDataStream.Write

Declaration: `function Write(const Buffer; Count: LongInt) : LongInt; Override`

Visibility: `public`

### 19.4.9 TCachedDataStream.Seek

Declaration: `function Seek(const Offset: Int64; Origin: TSeekOrigin) : Int64  
; Override`

Visibility: `public`

## 19.5 TCachedResourceDataStream

### 19.5.1 Description

This class provides an implementation of [TCachedDataStream \(118\)](#).

Usually resource readers create a [TResourceDataStream \(120\)](#) with a [TCachedResourceDataStream](#) as the underlying stream.

See also: [TCachedDataStream \(118\)](#), [TResourceDataStream \(120\)](#)

### 19.5.2 Method overview

Page	Method	Description
<a href="#">120</a>	Create	
<a href="#">120</a>	Read	



### 19.5.3 TCachedResourceDataStream.Create

Declaration: constructor Create(aStream: TStream; aResource: TAbstractResource;  
aSize: Int64); Override

Visibility: public

### 19.5.4 TCachedResourceDataStream.Read

Declaration: function Read(var Buffer; Count: LongInt) : LongInt; Override

Visibility: public

## 19.6 TResourceDataStream

### 19.6.1 Description

This class provides the copy-on-write mechanism of TAbstractResource.RawData (117), via more levels of indirection.

It uses an underlying stream, to which it redirects operations.

The underlying stream can be a TCachedDataStream (118) descendant, a memory stream or a custom stream. Usually when a resource is loaded from a stream, the underlying stream is a TCachedDataStream (118) descendant, which provides a read-only stream-like interface over a portion of the original stream (that is, the part of the original stream where resource data resides). When TResourceDataStream (120) is requested to write data, it replaces the underlying stream with a memory stream, whose contents are copied from the previous underlying stream: this way, copy-on-write functionality can be achieved.

As said before, third possibility is to have a custom stream as the underlying stream: a user can set this stream via TAbstractResource.SetCustomRawDataStream (117) method, which in turn calls TResourceDataStream.SetCustomStream (122)

**Figure:** Levels of indirection



See also: TCachedDataStream (118), TResourceDataStream.Create (121), TResourceDataStream.SetCustomStream (122)

### 19.6.2 Method overview

Page	Method	Description
<a href="#">122</a>	Compare	Compares the stream to another one
<a href="#">121</a>	Create	Creates a new object
<a href="#">122</a>	Destroy	
<a href="#">121</a>	GetPosition	
<a href="#">121</a>	GetSize	
<a href="#">122</a>	Read	
<a href="#">123</a>	Seek	
<a href="#">122</a>	SetCustomStream	Sets a custom stream as the underlying stream
<a href="#">121</a>	SetPosition	
<a href="#">121</a>	SetSize64	
<a href="#">122</a>	Write	

### 19.6.3 Property overview

Page	Properties	Access	Description
<a href="#">123</a>	Cached	rw	Controls the copy-on-write behaviour of the stream

### 19.6.4 TResourceDataStream.GetPosition

Declaration: `function GetPosition : Int64; Override`

Visibility: `protected`

### 19.6.5 TResourceDataStream.SetPosition

Declaration: `procedure SetPosition(const Pos: Int64); Override`

Visibility: `protected`

### 19.6.6 TResourceDataStream.GetSize

Declaration: `function GetSize : Int64; Override`

Visibility: `protected`

### 19.6.7 TResourceDataStream.SetSize64

Declaration: `procedure SetSize64(const NewSize: Int64); Override`

Visibility: `protected`

### 19.6.8 TResourceDataStream.Create

Synopsis: Creates a new object

Declaration: `constructor Create(aStream: TStream; aResource: TAbstractResource;  
aSize: Int64; aClass: TCachedStreamClass)`

Visibility: `public`

Description: A new `TResourceDataStream` ([120](#)) object is created.

If `aStream` is `nil`, the underlying stream is a memory stream. Otherwise, a cached stream of the class specified in `aClass` is created and set as the underlying stream.

See also: `TResourceDataStream` ([120](#)), `TCachedDataStream` ([118](#)), `TResourceDataStream.SetCustomStream` ([122](#))

### 19.6.9 TResourceDataStream.Destroy

Declaration: `destructor Destroy; Override`

Visibility: `public`

### 19.6.10 TResourceDataStream.Compare

Synopsis: Compares the stream to another one

Declaration: `function Compare(aStream: TStream) : Boolean`

Visibility: `public`

Description: This methods compares the stream with `aStream`. If they are of the same length and their contents are the same, `true` is returned, `false` otherwise.

See also: `TAbstractResource.CompareContents` ([117](#))

### 19.6.11 TResourceDataStream.SetCustomStream

Synopsis: Sets a custom stream as the underlying stream

Declaration: `procedure SetCustomStream(aStream: TStream)`

Visibility: `public`

Description: This method sets a custom stream as the underlying stream.

If `aStream` is `nil`, a new memory stream is used as the underlying stream. This can be used to remove a previously set custom stream as the underlying stream.

Usually it is called by `TAbstractResource.SetCustomRawDataStream` ([117](#)).

See also: `TResourceDataStream` ([120](#)), `TAbstractResource.SetCustomRawDataStream` ([117](#))

### 19.6.12 TResourceDataStream.Read

Declaration: `function Read(var Buffer; Count: LongInt) : LongInt; Override`

Visibility: `public`

### 19.6.13 TResourceDataStream.Write

Declaration: `function Write(const Buffer; Count: LongInt) : LongInt; Override`

Visibility: `public`

### 19.6.14 TResourceDataStream.Seek

Declaration: `function Seek(const Offset: Int64; Origin: TSeekOrigin) : Int64  
; Override`

Visibility: public

### 19.6.15 TResourceDataStream.Cached

Synopsis: Controls the copy-on-write behaviour of the stream

Declaration: `Property Cached : Boolean`

Visibility: public

Access: Read,Write

Description: When this property is set to `true`, a cached stream is used as the underlying stream for read operations. If it is set to `false`, no caching is performed and data is always copied to a memory stream.

Note that this property does nothing if the underlying stream is a custom stream.

By default this property is `true`.

See also: `TResourceDataStream` ([120](#)), `TAbstractResource.CacheData` ([117](#))

## Chapter 20

# Reference for unit 'resfactory'

### 20.1 Used units

Table 20.1: Used units by unit 'resfactory'

Name	Page
Classes	??
resource	<a href="#">127</a>
System	??
sysutils	??

### 20.2 Overview

This unit contains a factory class that provides an easy way to create resources of the right class.

Resource classes can be registered with `TResourceFactory` ([125](#)) so that the class knows how to create a resource of a specific type.

### 20.3 Constants, types and variables

#### 20.3.1 Resource strings

```
SAlreadyRegistered =  
    'A resource class for the type %s is already registered.'
```

### 20.4 `EResourceClassAlreadyRegisteredException`

#### 20.4.1 Description

This exception is raised by class method `RegisterResourceClass` ([125](#)) of `TResourceFactory` ([125](#)) when an attempt is made to register a class for an already registered type.

See also: `TResourceFactory.RegisterResourceClass` ([125](#))

## 20.5 EResourceFactoryException

### 20.5.1 Description

## Base class for resource factory-related exceptions

## 20.6 TResourceFactory

### 20.6.1 Description

Resources are represented by descendants of `TAbstractResource` (124). Some applications don't need specialized resource classes, and a `TGenericResource` (124) can be enough. On the other hand, sometimes it is required that a resource of a specific type is created with a more specialized class. This class provides a centralized point for the creation of resources.

TResourceFactory (125) holds a list of registered classes with an associated resource type. When it is requested to create a resource for a given type, it creates a resource of the class associated with that type. If no class matching that type is found, TGenericResource (124) is used.

Usually each resource class registers itself in the `initialization` section of the unit in which it is implemented.

: TResourceFactory.RegisterResourceClass (125), TResourceFactory.CreateResource (125), TAbstractResource (124), TGenericResource (124)

### 20.6.2 Method overview

Page	Method	Description
<a href="#">125</a>	CreateResource	Creates a new resource
<a href="#">125</a>	RegisterResourceClass	Registers a resource class

### 20.6.3 TResourceFactory.RegisterResourceClass

: Registers a resource class

[illegible]

: public

: This class method registers a resource class for the given resource type.

: If a class has already been registered for the given resource type, an `EResourceClassAlreadyRegisteredException` (124) exception is raised.

: TResourceFactory (125)

## 20.6.4 TResourceFactory.CreateResource

: Creates a new resource

**Declaration:** `class function CreateResource(aType: TResourceDesc;  
aName: TResourceDesc) : TAbstractResource`

**Visibility:** public

**Description:** This class method creates a new resource of the class associated with the given type, and sets its name and type based on the values passed as parameters.

If no class matching the given type is found, the resource is created with `TGenericResource` ([124](#)) class.

**See also:** `TResourceFactory` ([125](#)), `TResourceFactory.RegisterResourceClass` ([125](#)), `TGenericResource` ([124](#))

# Chapter 21

## Reference for unit 'resource'

### 21.1 Used units

Table 21.1: Used units by unit 'resource'

Name	Page
Classes	??
System	??
sysutils	??

### 21.2 Overview

This unit contains base classes needed to work with resources.

Single resources are represented by an instance of a `TAbstractResource` (133) descendant. They are grouped in a `TResources` (154) instance which can be read (written) to (from) a stream via a `TAbstractResourceReader` (143) (`TAbstractResourceWriter` (148)) descendant.

`TGenericResource` (150) provides a basic implementation of `TAbstractResource` (133).

### 21.3 Constants, types and variables

#### 21.3.1 Resource strings

```
SDescChangeNotAllowed = 'Cannot modify %s resource description'
```

```
SLangIDChangeNotAllowed = 'Cannot modify %s resource language ID'
```

```
SReaderNotFoundExt =  
  'Cannot find resource reader for extension ''%s'''
```

```
SReaderNotFoundProbe =  
  'Cannot find a resource reader: unknown format.'
```



```
SResDuplicate =
    'Duplicate resource: Type = %s, Name = %s, Lang ID = %.4x'

SResourceNotFound = 'Cannot find resource: Type = %s, Name = %s'

SResourceNotFoundLang =
    'Cannot find resource: Type = %s, Name = %s, Lang ID = %.4x'

SWriterNotFoundExt =
    'Cannot find resource writer for extension ''%s'''
```

### 21.3.2 Constants

```
CREATEPROCESS_MANIFEST_RESOURCE_ID = 1
```

```
ISOLATIONAWARE_MANIFEST_RESOURCE_ID = 2
```

```
ISOLATIONAWARE_NOSTATICIMPORT_MANIFEST_RESOURCE_ID = 3
```

```
MAXIMUM_RESERVED_MANIFEST_RESOURCE_ID = 16
```

```
MF_DISCARDABLE = $1000
```

This flag is ignored by Windows and Free Pascal RTL. It's provided for compatibility with 16-bit Windows.

```
MF_MOVEABLE = $0010
```

This flag is ignored by Windows and Free Pascal RTL. It's provided for compatibility with 16-bit Windows.

```
MF_PRELOAD = $0040
```

This flag is ignored by Windows and Free Pascal RTL. It's provided for compatibility with 16-bit Windows.

```
MF_PURE = $0020
```

This flag is ignored by Windows and Free Pascal RTL. It's provided for compatibility with 16-bit Windows.

```
MINIMUM_RESERVED_MANIFEST_RESOURCE_ID = 1
```

```
RT_ACCELERATOR = 9
```

Accelerator table resource

RT\_ANICURSOR = 21

This resource type contains raw binary data taken from a .ani file

RT\_ANIICON = 22

This resource type contains raw binary data taken from a .ani file

RT\_BITMAP = 2

Bitmap resource

RT\_CURSOR = 1

A single image in a cursor. Don't use it directly.

RT\_DIALOG = 5

Dialog resource

RT\_DLGINCLUDE = 17

This resource is used internally by resource compilers but will never appear in compiled form

RT\_FONT = 8

This resource type is obsolete and never appears in 32 bit resources.

RT\_FONTDIR = 7

This resource type is obsolete and never appears in 32 bit resources.

RT\_GROUP\_CURSOR = 12

This resource type contains a cursor and it's the equivalent of a .cur file

**Remark:** Please note that is is made up of several RT\_CURSOR ([129](#)) resources (the single cursor images) that shouldn't be accessed singularly.

RT\_GROUP\_ICON = 14

This resource type contains an icon and it's the equivalent of a .ico file

**Remark:** Please note that is is made up of several RT\_ICON ([130](#)) resources (the single icon images) that shouldn't be accessed singularly.

RT\_HTML = 23

This resource type contains an HTML file.

RT\_ICON = 3

A single image in a icon. Don't use it directly.

RT\_MANIFEST = 24

This resource contains data taken from a .manifest file

**Remark:** Resource name must be one of CREATEPROCESS\_MANIFEST\_RESOURCE\_ID (128) (mainly used for executables), ISOLATIONAWARE\_MANIFEST\_RESOURCE\_ID (128) or ISOLATION-AWARE\_NOSTATICIMPORT\_MANIFEST\_RESOURCE\_ID (128) (mainly used for DLLs)

RT\_MENU = 4

Menu resource

RT\_MESSAGE\_TABLE = 11

Message table resource

RT\_PLUGPLAY = 19

Plug and Play resource

RT\_RC\_DATA = 10

This resource type contains arbitrary binary data

Note that Delphi dfm files are stored in compiled form as a RC\_DATA resource

RT\_STRING = 6

String table resource

RT\_VERSION = 16

This resource defines version information which is visible when viewing properties of a Windows executable or DLL.

RT\_VXD = 20

VXD resource

### 21.3.3 Types

TDescType = (dtName, dtID)

Table 21.2: Enumeration values for type TDescType

Value	Explanation
dtID	The resource type or name is an ID
dtName	The resource type or name is a string

The type of a resource type or name

`TLangID = Word`

A resource language ID

`TResID = LongWord`

A resource type or name in ID form

`TResName = String`

A resource type or name in string form

`TResourceClass = Class of TAbstractResource`

Resource metaclass

`TResourceReaderClass = Class of TAbstractResourceReader`

Resource reader metaclass

`TResourceWriterClass = Class of TAbstractResourceWriter`

Resource writer metaclass

## 21.4 ENoMoreFreeIDsException

### 21.4.1 Description

This exception is raised by `TResources.AddAutoID` ([156](#)) method when it is not possible to generate an ID to use as a name for the given resource, because all possible 65536 IDs are already assigned to resources of the same type as the given one.

See also: `TResources.AddAutoID` ([156](#))

## 21.5 EResourceDescChangeNotAllowedException

### 21.5.1 Description

This exception is raised when a resource description (either type or name) is tried to be changed, but the resource class doesn't allow it.

See also: `TAbstractResource._Type` ([139](#)), `TAbstractResource.Name` ([139](#))

## 21.6 EResourceDescTypeException

### 21.6.1 Description

This exception is raised when a resource description is of type `dtName` ([130](#)) and `TResourceDesc.ID` ([154](#)) property is read.

See also: `TResourceDesc.ID` ([154](#))

## 21.7 EResourceDuplicateException

### 21.7.1 Description

This exception is raised when a resource is being added to a TResources (154) object, but another resource with the same type, name and language ID already exists.

See also: TResources.Add (155), TResources.MoveFrom (157)

## 21.8 EResourceException

### 21.8.1 Description

Base class for resource-related exceptions

## 21.9 EResourceLangIDChangeNotAllowedException

### 21.9.1 Description

This exception is raised when the resource language ID is tried to be changed, but the resource is contained in a TResources (154) object.

See also: TAbstractResource.LangID (139)

## 21.10 EResourceNotFoundException

### 21.10.1 Description

This exception is raised when searching for a resource in a TResources (154) object fails.

See also: TResources.Find (156), TResources.Remove (157)

## 21.11 EResourceReaderException

### 21.11.1 Description

Base class for resource reader-related exceptions

## 21.12 EResourceReaderNotFoundException

### 21.12.1 Description

This exception is raised when no TAbstractResourceReader (143) descendant able to read a stream was found.

See also: TResources.FindReader (157), TResources.LoadFromStream (158), TResources.LoadFromFile (158)

## 21.13 EResourceReaderUnexpectedEndOfStreamException

### 21.13.1 Description

This exception is raised by Load (146) method of a TAbstractResourceReader (143) descendant when the stream it was asked to read resources from ended prematurely.

See also: TAbstractResourceReader.Load (146)

## 21.14 EResourceReaderWrongFormatException

### 21.14.1 Description

This exception is raised by Load (146) method of a TAbstractResourceReader (143) descendant when the stream it was asked to read resources from is not in the format it supports.

See also: TAbstractResourceReader.Load (146)

## 21.15 EResourceWriterException

### 21.15.1 Description

Base class for resource writer-related exceptions

## 21.16 EResourceWriterNotFoundException

### 21.16.1 Description

This exception is raised by WriteToFile (160) method of TResources (154) when no TAbstractResourceWriter (148) descendant matching filename extension was found.

See also: TResources.WriteToFile (160)

## 21.17 TAbstractResource

### 21.17.1 Description

This is the base class that represents a resource.

A resource is identified by its type (139), name (139) and language ID (139) even if some file formats or operating systems don't consider the latter.

There are also additional properties that aren't always present in all file formats, so their values aren't always meaningful: however, they can be used to display detailed information when possible.

Every resource has a RawData (142) stream that holds resource data. This stream uses a copy-on-write mechanism: if the resource has been read from a stream or file, RawData (142) redirects read operations to the original stream. This is particularly useful when a resource file must be converted from a format to another, or when more resource files must be merged, since (potentially large) resource data is directly copied from the original to the destination stream without the need of allocating a lot of memory.

When resource data is encoded in a resource-specific format, `RawData` (142) can be uncomfortable: it's often better to use a more specialized descendant class that provides additional properties and methods.

Resources cannot be read or written alone from/to a stream: they need to be contained in a `TResources` (154) object, which represents an abstract view of a resource file.

Usually each descendant registers itself with `TResourceFactory` (127) class in the `initialization` section of the unit in which it is implemented: this way `TResourceFactory` (127) class can know which class to use to instantiate a resource of a given type.

**Remark:** An object of this class should never be directly instantiated: use a descendant class instead.

See also: `TGenericResource` (150), `TAcceleratorsResource` (127), `TBitmapResource` (127), `TGroupCursorResource` (127), `TGroupIconResource` (127), `TStringTableResource` (127), `TVersionResource` (127), `TResources` (154), `TResourceFactory` (127)

### 21.17.2 Method overview

Page	Method	Description
136	<code>ChangeDescTypeAllowed</code>	Reports whether changing the type of resource type or name is allowed
136	<code>ChangeDescValueAllowed</code>	Reports whether changing the value of resource type or name is allowed
137	<code>CompareContents</code>	Compares the contents of the resource to the contents of another one
137	<code>Create</code>	Creates a new resource
137	<code>Destroy</code>	Destroys the object
136	<code>GetName</code>	Returns the name of the resource
135	<code>GetType</code>	Returns the type of the resource
137	<code>NotifyResourcesLoaded</code>	Tells the resource that all resources have been loaded
135	<code>SetChildOwner</code>	Protected method to let a resource set itself as the owner of a sub-resource
138	<code>SetCustomRawDataStream</code>	Sets a custom stream as the underlying stream for <code>RawData</code>
135	<code>SetDescOwner</code>	Sets this resource as the owner of the given <code>TResourceDesc</code>
135	<code>SetOwnerList</code>	Protected method to let a resource list set itself as the owner of the resource
138	<code>UpdateRawData</code>	Updates <code>RawData</code> stream.

### 21.17.3 Property overview

Page	Properties	Access	Description
<a href="#">142</a>	CacheData	rw	Controls the copy-on-write behaviour of the resource
<a href="#">141</a>	Characteristics	rw	A user defined piece of data
<a href="#">141</a>	CodePage	rw	The code page of the resource
<a href="#">141</a>	DataOffset	r	The offset of resource data from the beginning of the stream
<a href="#">139</a>	DataSize	r	The size of resource raw data
<a href="#">140</a>	DataVersion	rw	The version of the resource data
<a href="#">140</a>	HeaderSize	r	The size of resource header
<a href="#">139</a>	LangID	rw	The language ID of the resource
<a href="#">140</a>	MemoryFlags	rw	The memory flags of the resource
<a href="#">139</a>	Name	r	The name of the resource
<a href="#">143</a>	Owner	r	The owner of this resource
<a href="#">142</a>	OwnerList	r	The resource list that owns this resource
<a href="#">142</a>	RawData	r	The raw resource data stream
<a href="#">141</a>	Version	rw	A user defined version number
<a href="#">139</a>	\_Type	r	The type of the resource

### 21.17.4 TAbstractResource.SetDescOwner

Synopsis: Sets this resource as the owner of the given TResourceDesc

Declaration: `procedure SetDescOwner(aDesc: TResourceDesc)`

Visibility: protected

Description: This method is provided so that descendants of TAbstractResource ([133](#)) can set themselves as the owners of the given TResourceDesc

### 21.17.5 TAbstractResource.SetOwnerList

Synopsis: Protected method to let a resource list set itself as the owner of the resource

Declaration: `procedure SetOwnerList(aResources: TResources); Virtual`

Visibility: protected

### 21.17.6 TAbstractResource.SetChildOwner

Synopsis: Protected method to let a resource set itself as the owner of a sub-resource

Declaration: `procedure SetChildOwner(aChild: TAbstractResource)`

Visibility: protected

### 21.17.7 TAbstractResource.GetType

Synopsis: Returns the type of the resource

Declaration: `function GetType : TResourceDesc; Virtual; Abstract`

Visibility: protected

Description: Descendant classes must implement this method to provide access to the resource type.



### 21.17.8 TAbstractResource.GetName

Synopsis: Returns the name of the resource

Declaration: `function GetName : TResourceDesc; Virtual; Abstract`

Visibility: protected

Description: Descendant classes must implement this method to provide access to the resource name.

### 21.17.9 TAbstractResource.ChangeDescTypeAllowed

Synopsis: Reports whether changing the type of resource type or name is allowed

Declaration: `function ChangeDescTypeAllowed(aDesc: TResourceDesc) : Boolean; Virtual  
; Abstract`

Visibility: protected

Description: Descendant classes must implement this method to declare if the resource allows changing the type of one of its resource description (type or name): that is, if it allows one of its descriptions type to change from dtName (130) to dtID (130) or vice versa.

**Example:**

A certain resource class allows its name only to be changed: e.g. a TBitmapResource (127) doesn't want its type to be anything else than RT\_BITMAP (129). It then allows changing the type of the description only if the description is the resource name:

```
Result:=aDesc=fName;
```

See also: TAbstractResource.ChangDescValueAllowed (133)

### 21.17.10 TAbstractResource.ChangeDescValueAllowed

Synopsis: Reports whether changing the value of resource type or name is allowed

Declaration: `function ChangeDescValueAllowed(aDesc: TResourceDesc) : Boolean  
; Virtual; Abstract`

Visibility: protected

Description: Descendant classes must implement this method to declare if the resource allows changing the value of one of its resource description (type or name).

**Example:**

A certain resource class allows its name only to be changed: e.g. a TBitmapResource (127) doesn't want its type to be anything else than RT\_BITMAP (129). It then allows changing the value of the description only if the description is the resource name:

```
Result:=aDesc=fName;
```

See also: TAbstractResource.ChangDescTypeAllowed (133)

### 21.17.11 TAbstractResource.NotifyResourcesLoaded

Synopsis: Tells the resource that all resources have been loaded

Declaration: `procedure NotifyResourcesLoaded; Virtual; Abstract`

Visibility: `protected`

Description: This method is called by a TResources (154) object when the loading of all resources from a stream has completed.

**Example:**

A Group resource (e.g. TGroupIconResource (127)) can use this method to find all its sub-resources, since all resources have been loaded from a stream.

### 21.17.12 TAbstractResource.Create

Synopsis: Creates a new resource

Declaration: `constructor Create; Virtual; Overload  
constructor Create(aType: TResourceDesc; aName: TResourceDesc); Virtual  
; Abstract; Overload`

Visibility: `protected`

Description: A new resource is created with the given type and name.

**Remark:** Please note that the resource doesn't take ownership of the TResourceDesc (152) objects passed as parameters, it simply copies them: it's user responsibility to free them when no longer needed.

### 21.17.13 TAbstractResource.Destroy

Synopsis: Destroys the object

Declaration: `destructor Destroy; Override`

Visibility: `public`

### 21.17.14 TAbstractResource.CompareContents

Synopsis: Compares the contents of the resource to the contents of another one

Declaration: `function CompareContents(aResource: TAbstractResource) : Boolean  
; Virtual`

Visibility: `public`

Description: This methods compares the contents of the resource with the ones of aResource. If they are of the same length and their contents are the same, true is returned, false otherwise.

Usually this methods compares the contents of the two RawData (142) streams, calling TResourceDataStream.Compare (127), but descendent classes can implement a different algorithm.

See also: TResourceDataStream.Compare (127)

**21.17.15 TAbstractResource.UpdateRawData**

Synopsis: Updates RawData stream.

Declaration: `procedure UpdateRawData; Virtual; Abstract`

Visibility: `public`

Description: When operating on resource data with more high-level streams than RawData (142) (e.g. TBitmapResource.BitmapData (127)) RawData contents are no longer valid. This method ensures that RawData (142) stream is properly synchronized with the contents of the higher-level stream.

**Remark:** Normally a resource writer doesn't need to call this method when it is about to write the resource data to a stream, since TResources (154) class takes care of this before telling the resource writer to write resources to a stream.

See also: TAbstractResource.RawData (142)

**21.17.16 TAbstractResource.SetCustomRawDataStream**

Synopsis: Sets a custom stream as the underlying stream for RawData

Declaration: `procedure SetCustomRawDataStream(aStream: TStream)`

Visibility: `public`

Description: Normally, RawData (142) uses a memory stream or the original resource stream (e.g. the original file containing the resource) as its underlying stream. This method allows the user to use a custom stream as the underlying stream. This can be useful when a resource must be created from the contents of an original file as-is.

If aStream is nil, a new memory stream is used as the underlying stream. This can be used to remove a previously set custom stream as the underlying stream.

**Sample code**

This code creates a resource containing an html file

```
var
  aType, aName : TResourceDesc;
  aRes : TGenericResource;
  aFile : TFileStream;
begin
  aType:=TResourceDesc.Create(RT_HTML);
  aName:=TResourceDesc.Create('index');
  aRes:=TGenericResource.Create(aType,aName);
  aFile:=TFileStream.Create('index.html',fmOpenRead or fmShareDenyNone);
  aRes.SetCustomRawDataStream(aFile);

  //do something...

  aRes.Free;
  aFile.Free;
  aType.Free;
  aName.Free;
end;
```

See also: TAbstractResource.RawData (142)

### 21.17.17 TAbstractResource.\_Type

Synopsis: The type of the resource

Declaration: `Property _Type : TResourceDesc`

Visibility: public

Access: Read

**Description:** Please note that some `TAbstractResource` (133) descendants don't allow resource type to be changed (e.g: it's not possible for a `TBitmapResource` (127) to have a type other than `RT_BITMAP` (129)). If it is the case, an `EResourceDescChangeNotAllowedException` (131) exception is raised.

Moreover, if the resource is contained in a `TResources` (154) object, type change is not allowed.

See also: `TAbstractResource.ChangeDescTypeAllowed` (136), `TAbstractResource.ChangeDescValueAllowed` (136)

### 21.17.18 TAbstractResource.Name

Synopsis: The name of the resource

Declaration: `Property Name : TResourceDesc`

Visibility: public

Access: Read

**Description:** Please note that some `TAbstractResource` (133) descendants don't allow resource name to be changed (e.g: a `TStringTableResource` (127) name is determined by the range of strings' ID it contains). If it is the case, an `EResourceDescChangeNotAllowedException` (131) exception is raised.

Moreover, if the resource is contained in a `TResources` (154) object, name change is not allowed.

See also: `TAbstractResource.ChangeDescTypeAllowed` (136), `TAbstractResource.ChangeDescValueAllowed` (136)

### 21.17.19 TAbstractResource.LangID

Synopsis: The language ID of the resource

Declaration: `Property LangID : TLangID`

Visibility: public

Access: Read,Write

**Description:** Please note that if the resource is contained in a `TResources` (154) object, language ID change is not allowed: trying to do so results in an `EResourceLangIDChangeNotAllowedException` (132) exception being raised.

### 21.17.20 TAbstractResource.DataSize

Synopsis: The size of resource raw data

Declaration: `Property DataSize : LongWord`

Visibility: public

Access: Read

Description: DataSize is the length, in bytes, of the resource data, accessible via RawData ([142](#)) property.

See also: TAbstractResource.RawData ([142](#)), TAbstractResource.DataOffset ([141](#))

### 21.17.21 TAbstractResource.HeaderSize

Synopsis: The size of resource header

Declaration: `Property HeaderSize : LongWord`

Visibility: public

Access: Read

Description: This property is not always meaningful, since not all file formats support it.

Its value, when nonzero, can be used for information purposes.

### 21.17.22 TAbstractResource.DataVersion

Synopsis: The version of the resource data

Declaration: `Property DataVersion : LongWord`

Visibility: public

Access: Read,Write

Description: This property is not always meaningful, since not all file formats support it.

Its value, when nonzero, can be used for information purposes.

### 21.17.23 TAbstractResource.MemoryFlags

Synopsis: The memory flags of the resource

Declaration: `Property MemoryFlags : Word`

Visibility: public

Access: Read,Write

Description: This field is a combination of the following flags

- MF\_MOVEABLE ([128](#))
- MF\_PURE ([128](#))
- MF\_PRELOAD ([128](#))
- MF\_DISCARDABLE ([128](#))

By default, a newly created resource has MF\_MOVEABLE ([128](#)) and MF\_DISCARDABLE ([128](#)) flags set.

**Remark:** Please note that memory flags are ignored by Windows and Free Pascal RTL. They are provided only for compatibility with 16-bit Windows.

This property is not always meaningful, since not all file formats support it.

Its value, when nonzero, can be used for information purposes.

#### **21.17.24 TAbstractResource.Version**

Synopsis: A user defined version number

Declaration: `Property Version : LongWord`

Visibility: public

Access: Read,Write

Description: A tool that writes resource files can write version information in this field.

This property is not always meaningful, since not all file formats support it.

Its value, when nonzero, can be used for information purposes.

See also: `TAbstractResource.Characteristics` ([141](#))

#### **21.17.25 TAbstractResource.Characteristics**

Synopsis: A user defined piece of data

Declaration: `Property Characteristics : LongWord`

Visibility: public

Access: Read,Write

Description: A tool that writes resource files can write arbitrary data in this field.

This property is not always meaningful, since not all file formats support it.

Its value, when nonzero, can be used for information purposes.

See also: `TAbstractResource.Version` ([141](#))

#### **21.17.26 TAbstractResource.DataOffset**

Synopsis: The offset of resource data from the beginning of the stream

Declaration: `Property DataOffset : LongWord`

Visibility: public

Access: Read

Description: A reader sets this property to let the resource know where its raw data begins in the resource stream.

See also: `TAbstractResource.RawData` ([142](#)), `TAbstractResource.DataSize` ([139](#))

#### **21.17.27 TAbstractResource.CodePage**

Synopsis: The code page of the resource

Declaration: `Property CodePage : LongWord`

Visibility: public

Access: Read,Write

Description: This property is not always meaningful, since not all file formats support it.

Its value, when nonzero, can be used for information purposes.

### 21.17.28 TAbstractResource.RawData

Synopsis: The raw resource data stream

Declaration: `Property RawData : TStream`

Visibility: public

Access: Read

Description: This property provides access to the resource raw data in a stream-like way.

When a resource has been read from a stream, RawData redirects read operations to the original stream. When RawData is written to, a copy-on-write mechanism copies data from the original stream to a memory stream.

The copy-on-write behaviour can be controlled via CacheData (142) property.

Note that for some predefined resource types there are better ways to read and write resource data: some resource types use specific formats, so RawData might not always be what one expected. E.g. in a resource of type RT\_BITMAP (129), RawData doesn't contain a valid BMP file: in this case it's better to use BitmapData (127) stream of TBitmapResource (127) class to work with a BMP-like stream.

**Remark:** When writing to a "specialized" stream in a descendant class (like the TBitmapResource.BitmapData (127) stream mentioned earlier), RawData contents might not be valid anymore. If you need to access RawData again, be sure to call UpdateRawData (138) method first.

Usually there isn't much penalty in using specialized streams in descendant classes, since data isn't duplicated in two or more streams, whenever possible. So, having a very large bitmap resource and reading/writing it via TBitmapResource.BitmapData (127) doesn't mean the bitmap is allocated two times.

See also: TAbstractResource.CacheData (142), TAbstractResource.UpdateRawData (138), TAbstractResource.SetCustomRawDataStream (138)

### 21.17.29 TAbstractResource.CacheData

Synopsis: Controls the copy-on-write behaviour of the resource

Declaration: `Property CacheData : Boolean`

Visibility: public

Access: Read,Write

Description: When CacheData is true, copy-on-write mechanism of RawData (142) is enabled.

Setting CacheData to false forces the raw resource data to be loaded in memory without performing any caching.

By default, CacheData is true.

See also: TAbstractResource.RawData (142), TResources.CacheData (161)

### 21.17.30 TAbstractResource.OwnerList

Synopsis: The resource list that owns this resource

Declaration: `Property OwnerList : TResources`

Visibility: public

Access: Read

Description: This property identifies the `TResources` (154) object to which this resource belongs to.

This property can be `nil` if the resource isn't part of a resource list.

### 21.17.31 TAbstractResource.Owner

Synopsis: The owner of this resource

Declaration: `Property Owner : TAbstractResource`

Visibility: `public`

Access: Read

Description: This property is meaningful only for those sub-resources that are part of a larger *group resource*.

**Example:** an icon is made by a `RT_GROUP_ICON` (129) resource and many `RT_ICON` (130) resources that hold single-image data. Each `RT_ICON` (130) resource has a pointer to the `RT_GROUP_ICON` (129) resource in its `Owner` property.

## 21.18 TAbstractResourceReader

### 21.18.1 Description

This is the base class that represents a resource reader.

A resource reader is an object whose job is to populate a `TResources` (154) object with resources read from a stream in a specific format.

Typically, a `TResources` (154) object invokes `CheckMagic` (147) method of the resource reader when it's searching for a reader able to read a certain stream, and `Load` (146) method when it wants the reader to read data from the stream.

Usually each resource reader registers itself with `TResources` (154) class in the `initialization` section of the unit in which it is implemented: this way a `TResources` (154) object can find it when probing a stream that is to be read.

**Remark:** An object of this class should never be directly instantiated: use a descendant class instead.

See also: `TResources` (154), `TAbstractResource` (133), `TAbstractResourceWriter` (148), `TResResourceReader` (127), `TCoffResourceReader` (127), `TWinPEResourceReader` (127), `TElfResourceReader` (127), `TEternalResourceReader` (127), `TDfmResourceReader` (127)



**21.18.2 Method overview**

Page	Method	Description
<a href="#">145</a>	AddNoTree	Adds a resource without updating the internal tree
<a href="#">145</a>	CallSubReaderLoad	Calls another reader's Load ( <a href="#">146</a> ) method
<a href="#">147</a>	CheckMagic	Checks whether a stream is in a format the reader recognizes
<a href="#">147</a>	Create	Creates a new reader object
<a href="#">146</a>	GetDescription	Returns the description of the reader
<a href="#">146</a>	GetExtensions	Returns the extensions the reader is registered for
<a href="#">146</a>	GetTree	Gets the internal resource tree of a TResources object
<a href="#">146</a>	Load	Loads resources from a stream
<a href="#">145</a>	SetDataOffset	Protected method to let a reader set a resource DataOffset ( <a href="#">141</a> ) property
<a href="#">144</a>	SetDataSize	Protected method to let a reader set a resource DataSize ( <a href="#">139</a> ) property
<a href="#">144</a>	SetHeaderSize	Protected method to let a reader set a resource HeaderSize ( <a href="#">140</a> ) property
<a href="#">145</a>	SetRawData	Protected method to let a reader set a resource RawData ( <a href="#">142</a> ) property

**21.18.3 Property overview**

Page	Properties	Access	Description
<a href="#">148</a>	Description	r	The reader description
<a href="#">147</a>	Extensions	r	The extensions of file types the reader is able to read

**21.18.4 TAbstractResourceReader.SetDataSize**

Synopsis: Protected method to let a reader set a resource DataSize ([139](#)) property

Declaration: `procedure SetDataSize(aResource: TAbstractResource; aValue: LongWord)`

Visibility: protected

Description: This method allows a descendant class to set DataSize ([139](#)) property of a resource that is being loaded.

See also: TAbstractResourceReader.SetHeaderSize ([144](#)), TAbstractResourceReader.SetDataOffset ([145](#)), TAbstractResourceReader.SetRawData ([145](#))

**21.18.5 TAbstractResourceReader.SetHeaderSize**

Synopsis: Protected method to let a reader set a resource HeaderSize ([140](#)) property

Declaration: `procedure SetHeaderSize(aResource: TAbstractResource; aValue: LongWord)`

Visibility: protected

Description: This method allows a descendant class to set HeaderSize ([140](#)) property of a resource that is being loaded.

See also: TAbstractResourceReader.SetDataSize ([144](#)), TAbstractResourceReader.SetDataOffset ([145](#)), TAbstractResourceReader.SetRawData ([145](#))

### 21.18.6 TAbstractResourceReader.SetDataOffset

Synopsis: Protected method to let a reader set a resource DataOffset (141) property

Declaration: `procedure SetDataOffset(aResource: TAbstractResource; aValue: LongWord)`

Visibility: protected

Description: This method allows a descendant class to set DataOffset (141) property of a resource that is being loaded.

See also: TAbstractResourceReader.SetDataSize (144), TAbstractResourceReader.SetHeaderSize (144), TAbstractResourceReader.SetRawData (145)

### 21.18.7 TAbstractResourceReader.SetRawData

Synopsis: Protected method to let a reader set a resource RawData (142) property

Declaration: `procedure SetRawData(aResource: TAbstractResource; aStream: TStream)`

Visibility: protected

Description: This method allows a descendant class to set RawData (142) property of a resource that is being loaded.

See also: TAbstractResourceReader.SetDataSize (144), TAbstractResourceReader.SetHeaderSize (144), TAbstractResourceReader.SetDataOffset (145)

### 21.18.8 TAbstractResourceReader.CallSubReaderLoad

Synopsis: Calls another reader's Load (146) method

Declaration: `procedure CallSubReaderLoad(aReader: TAbstractResourceReader;  
aResources: TResources; aStream: TStream)`

Visibility: protected

Description: This method allows a descendant class to call another reader's Load (146) method. This can be useful when a reader needs to use another one.

### 21.18.9 TAbstractResourceReader.AddNoTree

Synopsis: Adds a resource without updating the internal tree

Declaration: `procedure AddNoTree(aResources: TResources;  
aResource: TAbstractResource)`

Visibility: protected

Description: This protected method is used by descendants of TAbstractResourceReader (143) after they add new resources to the internal resource tree used by a TResources (154) object. Calling this method notifies the TResources (154) object about the newly-added resource.

See also: TAbstractResourceReader.GetTree (146), TRootResTreeNode (169)

### 21.18.10 TAbstractResourceReader.GetTree

Synopsis: Gets the internal resource tree of a TResources object

Declaration: `function GetTree(aResources: TResources) : TObject`

Visibility: protected

Description: This protected method can be used by descendants of TAbstractResourceReader (143) to obtain the internal resource tree used by a TResources (154) object. The internal resource tree is an instance of TRootResTreeNode (169).

Some resource readers can improve their performance if, instead of calling TResources.Add (155), add themselves resources to the internal tree used by a TResources (154) object.

**Remark:** After adding a resource to a resource tree, a reader must always call AddNoTree (145) method to let the TResources (154) object know about the newly-added resource.

See also: TAbstractResourceReader.AddNoTree (145), TRootResTreeNode (169)

### 21.18.11 TAbstractResourceReader.GetExtensions

Synopsis: Returns the extensions the reader is registered for

Declaration: `function GetExtensions : string; Virtual; Abstract`

Visibility: protected

Description: Descendant classes must implement this method to provide access to Extensions (147) property.

See also: TAbstractResourceReader.Extensions (147)

### 21.18.12 TAbstractResourceReader.GetDescription

Synopsis: Returns the description of the reader

Declaration: `function GetDescription : string; Virtual; Abstract`

Visibility: protected

Description: Descendant classes must implement this method to provide access to Description (148) property.

See also: TAbstractResourceReader.Description (148)

### 21.18.13 TAbstractResourceReader.Load

Synopsis: Loads resources from a stream

Declaration: `procedure Load(aResources: TResources; aStream: TStream); Virtual  
; Abstract`

Visibility: protected

Description: A TResources (154) object invokes this method when it needs to be loaded from a stream, passing itself as the aResources parameter and the stream as the aStream parameter.

aStream position is already correctly set: the reader must start to read from there.

Descendant classes must ensure that the stream is in a format they recognize, otherwise an EResourceReaderWrongFormatException (133) exception must be raised.

Each resource is then created, read from the stream and added to the TResources (154) object.

When reading a resource, a reader must:

- Create the resource via `TResourceFactory.CreateResource` (127) class method with the correct type and name.
- Set at least the following resource properties:
  - `DataSource` (139), via `SetDataSource` (144) method.
  - `DataOffset` (141), via `SetDataOffset` (145) method. This is the offset of the resource data from the beginning of the stream.
  - `RawData` (142). The reader must create a `TResourceDataStream` (127) object and assign it to the resource via `SetRawData` (145) method.

**Errors:** If the stream is in a format not recognized by the reader, a `EResourceReaderWrongFormatException` (133) exception must be raised.

If the stream ends prematurely, a `EResourceReaderUnexpectedEndOfStreamException` (133) exception must be raised.

**See also:** `TResources` (154), `TResources.LoadFromStream` (158), `TResources.LoadFromFile` (158), `TAbstractResource` (133), `TAbstractResource.DataSource` (139), `TAbstractResource.DataOffset` (141), `TAbstractResource.RawData` (142), `TAbstractResourceReader.SetDataSource` (144), `TAbstractResourceReader.SetDataOffset` (145), `TAbstractResourceReader.SetRawData` (145), `TAbstractResourceReader.CheckMagic` (147), `TResourceDataStream` (127)

#### 21.18.14 TAbstractResourceReader.CheckMagic

**Synopsis:** Checks whether a stream is in a format the reader recognizes

**Declaration:** `function CheckMagic(aStream: TStream) : Boolean; Virtual; Abstract`

**Visibility:** `protected`

**Description:** A `TResources` (154) object invokes this method when it is searching for a reader able to read a stream, passing that stream as the `aStream` parameter.

`aStream` position is already correctly set: the reader must start to read from there.

This method should read the minimum amount of information needed to recognize the contents of a stream as a valid format: it usually means reading a magic number or a file header.

**See also:** `TAbstractResourceReader.Load` (146), `TResources.FindReader` (157), `TResources.LoadFromStream` (158), `TResources.LoadFromFile` (158)

#### 21.18.15 TAbstractResourceReader.Create

**Synopsis:** Creates a new reader object

**Declaration:** `constructor Create; Virtual; Abstract`

**Visibility:** `public`

#### 21.18.16 TAbstractResourceReader.Extensions

**Synopsis:** The extensions of file types the reader is able to read

**Declaration:** `Property Extensions : string`

**Visibility:** `public`

**Access:** `Read`

**Description:** This property is a string made of space-separated file extensions (each including the leading dot), all lowercase.

This property signals which file types the reader is able to read.

### 21.18.17 TAbstractResourceReader.Description

**Synopsis:** The reader description

**Declaration:** `Property Description : string`

**Visibility:** public

**Access:** Read

**Description:** This property provides a textual description of the reader, e.g. "FOO resource reader"

## 21.19 TAbstractResourceWriter

### 21.19.1 Description

This is the base class that represents a resource writer.

A resource writer is an object whose job is to write all resources contained in a `TResources` (154) object to a stream in a specific format.

Typically, a `TResources` (154) object invokes `Write` (149) method of the resource writer when it wants the writer to write data to a stream.

Usually each resource writer registers itself with `TResources` (154) class in the `initialization` section of the unit in which it is implemented: this way a `TResources` (154) object can find it when it is asked to write itself to a file, and no writer was specified (the writer is found based on the extension of the file to write to).

**Remark:** An object of this class should never be directly instantiated: use a descendant class instead.

**See also:** `TResources` (154), `TAbstractResource` (133), `TAbstractResourceReader` (143), `TResResourceWriter` (127), `TCoffResourceWriter` (127), `TElfResourceWriter` (127), `TExternalResourceWriter` (127)

### 21.19.2 Method overview

Page	Method	Description
150	Create	Creates a new writer object
149	GetDescription	Returns the description of the writer
149	GetExtensions	Returns the extensions the writer is registered for
149	GetTree	Gets the internal resource tree of a <code>TResources</code> object
149	Write	Writes resources to a stream

### 21.19.3 Property overview

Page	Properties	Access	Description
150	Description	r	The writer description
150	Extensions	r	The extensions of file types the writer is able to write

### 21.19.4 TAbstractResourceWriter.GetTree

Synopsis: Gets the internal resource tree of a TResources object

Declaration: `function GetTree(aResources: TResources) : TObject`

Visibility: protected

Description: This protected method can be used by descendents of TAbstractResourceWriter (148) to obtain the internal resource tree used by a TResources (154) object. The internal resource tree is an instance of TRootResTreeNode (169).

Some resource writers need to order resources with a tree structure before writing them to a file. Instead of doing this work themselves, they can use the already-ordered internal resource tree of the TResources (154) object they must write.

See also: TRootResTreeNode (169)

### 21.19.5 TAbstractResourceWriter.GetExtensions

Synopsis: Returns the extensions the writer is registered for

Declaration: `function GetExtensions : string; Virtual; Abstract`

Visibility: protected

Description: Descendant classes must implement this method to provide access to Extensions (150) property.

See also: TAbstractResourceWriter.Extensions (150)

### 21.19.6 TAbstractResourceWriter.GetDescription

Synopsis: Returns the description of the writer

Declaration: `function GetDescription : string; Virtual; Abstract`

Visibility: protected

Description: Descendant classes must implement this method to provide access to Description (150) property.

See also: TAbstractResourceWriter.Description (150)

### 21.19.7 TAbstractResourceWriter.Write

Synopsis: Writes resources to a stream

Declaration: `procedure Write(aResources: TResources; aStream: TStream); Virtual  
; Abstract`

Visibility: protected

Description: A TResources (154) object invokes this method when it needs to be written to a stream, passing itself as the aResources parameter and the stream as the aStream parameter.

aStream position is already correctly set: the writer must start to write from there.

A writer must write data in the way specified by the format it supports: usually this means writing a header and all resources contained in the TResources (154) object.

For each resource, a writer should write some information about the resource (like type and name) in a way defined by the format it implements, and the resource data, which is accessible by RawData (142) property of the resource.

See also: [TResources \(154\)](#), [TResources.WriteToStream \(160\)](#), [TResources.WriteToFile \(160\)](#), [TAbstractResource \(133\)](#), [TAbstractResource.DataSize \(139\)](#), [TAbstractResource.RawData \(142\)](#)

### 21.19.8 TAbstractResourceWriter.Create

Synopsis: Creates a new writer object

Declaration: `constructor Create; Virtual; Abstract`

Visibility: `public`

### 21.19.9 TAbstractResourceWriter.Extensions

Synopsis: The extensions of file types the writer is able to write

Declaration: `Property Extensions : string`

Visibility: `public`

Access: `Read`

Description: This property is a string made of space-separated file extensions (each including the leading dot), all lowercase.

This property signals which file types the writer is able to write.

### 21.19.10 TAbstractResourceWriter.Description

Synopsis: The writer description

Declaration: `Property Description : string`

Visibility: `public`

Access: `Read`

Description: This property provides a textual description of the writer, e.g. "FOO resource writer"

## 21.20 TGenericResource

### 21.20.1 Description

This class represents a generic resource.

It is suitable to use in all situations where a higher level class is not needed (e.g. the resource raw data is made of arbitrary data) or when total low-level control is desirable.

This class is also the default one that is used by [TResourceFactory \(127\)](#) when it finds no class matching the given type.

See also: [TResourceFactory.CreateResource \(127\)](#)

### 21.20.2 Method overview

Page	Method	Description
<a href="#">151</a>	ChangeDescTypeAllowed	
<a href="#">151</a>	ChangeDescValueAllowed	
<a href="#">151</a>	Create	
<a href="#">152</a>	Destroy	
<a href="#">151</a>	GetName	
<a href="#">151</a>	GetType	
<a href="#">151</a>	NotifyResourcesLoaded	
<a href="#">152</a>	UpdateRawData	

### 21.20.3 TGenericResource.GetType

Declaration: `function GetType : TResourceDesc; Override`

Visibility: `protected`

### 21.20.4 TGenericResource.GetName

Declaration: `function GetName : TResourceDesc; Override`

Visibility: `protected`

### 21.20.5 TGenericResource.ChangeDescTypeAllowed

Declaration: `function ChangeDescTypeAllowed(aDesc: TResourceDesc) : Boolean  
; Override`

Visibility: `protected`

### 21.20.6 TGenericResource.ChangeDescValueAllowed

Declaration: `function ChangeDescValueAllowed(aDesc: TResourceDesc) : Boolean  
; Override`

Visibility: `protected`

### 21.20.7 TGenericResource.NotifyResourcesLoaded

Declaration: `procedure NotifyResourcesLoaded; Override`

Visibility: `protected`

### 21.20.8 TGenericResource.Create

Declaration: `constructor Create(aType: TResourceDesc; aName: TResourceDesc)  
; Override`

Visibility: `public`



### 21.20.9 TGenericResource.Destroy

Declaration: destructor Destroy; Override

Visibility: public

### 21.20.10 TGenericResource.UpdateRawData

Declaration: procedure UpdateRawData; Override

Visibility: public

## 21.21 TResourceDesc

### 21.21.1 Description

This class represent a resource description (type or name).

Resources are identified by a type, name and (optionally) a language ID.

Type and name can be either a **name** (a string identifier) or an **ID** (an integer identifier in the range 0..65535).

**Remark:** Unfortunately, *name* is used both to refer to a the name of the resource and both to the format of a resource description

**Example:**

Typically, a Windows executable has a main icon, which is a resource of type RT\_GROUP\_ICON (129) (type is an ID) and name MAINICON (name is a name).

See also: TAbstractResource (133)

### 21.21.2 Method overview

Page	Method	Description
<a href="#">153</a>	Assign	Assigns the contents of another TResourceDesc object to this one
<a href="#">153</a>	Create	Creates a new TResourceDesc object
<a href="#">153</a>	Equals	Compares the contents of another TResourceDesc object to this one
<a href="#">152</a>	SetOwner	Protected method to let a resource set itself as owner of the TResourceDesc

### 21.21.3 Property overview

Page	Properties	Access	Description
<a href="#">154</a>	DescType	r	The type of the resource description
<a href="#">154</a>	ID	rw	The value of the resource description as an ID
<a href="#">153</a>	Name	rw	The value of the resource description as a name

### 21.21.4 TResourceDesc.SetOwner

Synopsis: Protected method to let a resource set itself as owner of the TResourceDesc

Declaration: procedure SetOwner(aOwner: TAbstractResource)

Visibility: protected

### 21.21.5 TResourceDesc.Create

Synopsis: Creates a new TResourceDesc object

Declaration: `constructor Create; Overload`  
`constructor Create(const aID: TResID); Overload`  
`constructor Create(const aName: TResName); Overload`

Visibility: public

Description: Creates a new TResourceDesc object.

Without arguments, resource description is of type `dtName` (130) and its name is empty.

If an argument is specified, resource description and name/id are set accordingly to the value passed as parameter.

### 21.21.6 TResourceDesc.Assign

Synopsis: Assigns the contents of another TResourceDesc object to this one

Declaration: `procedure Assign(aResourceDesc: TResourceDesc)`

Visibility: public

Description: Assigns the contents of another TResourceDesc object to this one

Errors: If changing values is not permitted because owner resource doesn't allow it (e.g. because owner resource is a `TBitmapResource` (127) and values other than `RT_BITMAP` (129) are not permitted for the resource type) an `EResourceDescChangeNotAllowedException` (131) exception is raised.

### 21.21.7 TResourceDesc.Equals

Synopsis: Compares the contents of another TResourceDesc object to this one

Declaration: `function Equals(aResDesc: TResourceDesc) : Boolean`

Visibility: public

### 21.21.8 TResourceDesc.Name

Synopsis: The value of the resource description as a name

Declaration: `Property Name : TResName`

Visibility: public

Access: Read,Write

Description: Setting this property causes `DescType` (154) to be `dtName` (130)

When reading, if `DescType` (154) is `dtID` (130), the ID is returned as a string value.

See also: `TResourceDesc.ID` (154), `TResourceDesc.DescType` (154)

### 21.21.9 TResourceDesc.ID

Synopsis: The value of the resource description as an ID

Declaration: `Property ID : TResID`

Visibility: public

Access: Read, Write

Description: Setting this property causes DescType (154) to be dtID (130)

**Remark:** When reading, if DescType (154) is dtName (130), an EResourceDescTypeException (131) exception is raised.

See also: TResourceDesc.Name (153), TResourceDesc.DescType (154)

### 21.21.10 TResourceDesc.DescType

Synopsis: The type of the resource description

Declaration: `Property DescType : TDescType`

Visibility: public

Access: Read

Description: When DescType is dtName (130), resource description value is a name and can be accessed via Name (153) property

When DescType is dtID (130), resource description value is an ID and can be accessed via ID (154) property

See also: TResourceDesc.Name (153), TResourceDesc.ID (154), TDescType (130)

## 21.22 TResources

### 21.22.1 Description

This class represents a format-independent view of a resource file. It holds a collection of resources (TAbstractResource (133) descendants).

Typically, a TResource object is loaded from and written to a stream via format-dependent readers and writers, which are descendants of TAbstractResourceReader (143) and TAbstractResourceWriter (148), respectively.

Single resources can be added, removed, searched and modified: a resource compiler or editor probably will create resources, set their data, and add them to a TResources object which can then be written to file in the desired format.

This class also provides some class methods to register and find resource readers and writers: these classes, once registered, will be used by a TResources object when it is asked to load or save itself to a stream and the user didn't specify a reader or writer.

**Remark:** Because of the copy-on-write mechanism of TAbstractResource (133), care should be taken when loading resources, since by default resource data isn't immediately read from the stream: resources hold a reference to the original stream because they need it when their data is requested. For further information, see TResources.LoadFromStream (158) and TResources.LoadFromFile (158).

See also: TAbstractResource (133), TAbstractResourceReader (143), TAbstractResourceWriter (148)

### 21.22.2 Method overview

Page	Method	Description
<a href="#">155</a>	Add	Adds a resource
<a href="#">156</a>	AddAutoID	Adds a resource and gives it a new autogenerated name
<a href="#">156</a>	Clear	Deletes all resources
<a href="#">155</a>	Create	Creates a new TResources object
<a href="#">155</a>	Destroy	Destroys the object
<a href="#">156</a>	Find	Searches for a resource
<a href="#">157</a>	FindReader	Searches for a suitable resource reader
<a href="#">158</a>	LoadFromFile	Loads the contents of the object from a file
<a href="#">158</a>	LoadFromStream	Loads the contents of the object from a stream
<a href="#">157</a>	MoveFrom	Moves all resources of another TResources object to itself
<a href="#">159</a>	RegisterReader	Registers a resource reader class
<a href="#">159</a>	RegisterWriter	Registers a resource writer class
<a href="#">157</a>	Remove	Removes a resource
<a href="#">160</a>	WriteToFile	Writes the contents of the object to a file
<a href="#">160</a>	WriteToStream	Writes the contents of the object to a stream

### 21.22.3 Property overview

Page	Properties	Access	Description
<a href="#">161</a>	CacheData	rw	Controls the copy-on-write behaviour of all resources
<a href="#">160</a>	Count	r	The number of resources in the object
<a href="#">161</a>	Items	r	Indexed array of resources in the object

### 21.22.4 TResources.Create

Synopsis: Creates a new TResources object

Declaration: `constructor Create`

Visibility: `public`

### 21.22.5 TResources.Destroy

Synopsis: Destroys the object

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: All resources are destroyed as well.

### 21.22.6 TResources.Add

Synopsis: Adds a resource

Declaration: `procedure Add(aResource: TAbstractResource)`

Visibility: `public`

Description: This method adds `aResource` to the object, and sets itself as the owner list of the resource.

Errors: If a resource with the same type, name and language ID already exists, an `EResourceDuplicateException` ([132](#)) exception is raised.

See also: [TResources.AddAutoID \(156\)](#)

### 21.22.7 TResources.AddAutoID

Synopsis: Adds a resource and gives it a new autogenerated name

Declaration: `function AddAutoID(aResource: TAbstractResource) : TResID`

Visibility: public

Description: This method tries to find a spare ID to use as a name for the given resource, assigns it to the resource, and adds it.

This method is useful when the name of the resource is not important. E.g. a group resource doesn't care about the names of its sub-resources, so it could use this method to ensure that its sub-resources don't clash with names of other sub-resources of the same type.

Errors: If there are no more free IDs for the resource type of the given resource (that is, when the number of resources of the same type of `aResource` with an ID name is equal to 65536) an `ENoMoreFreeIDsException` ([131](#)) exception is raised.

See also: [TResources.Add \(155\)](#)

### 21.22.8 TResources.Clear

Synopsis: Deletes all resources

Declaration: `procedure Clear`

Visibility: public

Description: This method empties the `TResources` object destroying all resources.

### 21.22.9 TResources.Find

Synopsis: Searches for a resource

Declaration: `function Find(aType: TResourceDesc; aName: TResourceDesc;  
const aLangID: TLangID) : TAbstractResource; Overload  
function Find(aType: TResourceDesc; aName: TResourceDesc)  
: TAbstractResource; Overload  
function Find(const aType: TResName; const aName: TResName;  
const aLangID: TLangID) : TAbstractResource; Overload  
function Find(const aType: TResName; const aName: TResID;  
const aLangID: TLangID) : TAbstractResource; Overload  
function Find(const aType: TResID; const aName: TResName;  
const aLangID: TLangID) : TAbstractResource; Overload  
function Find(const aType: TResID; const aName: TResID;  
const aLangID: TLangID) : TAbstractResource; Overload  
function Find(const aType: TResName; const aName: TResName)  
: TAbstractResource; Overload  
function Find(const aType: TResName; const aName: TResID)  
: TAbstractResource; Overload  
function Find(const aType: TResID; const aName: TResName)  
: TAbstractResource; Overload  
function Find(const aType: TResID; const aName: TResID)  
: TAbstractResource; Overload`

Visibility: public

Description: This method searches for a resource with the given type and name. If a language ID is not provided, the first resource found that matches aType and aName is returned.

Errors: If the resource is not found, an EResourceNotFoundException (132) exception is raised.

### 21.22.10 TResources.FindReader

Synopsis: Searches for a suitable resource reader

Declaration: 

```
class function FindReader(aStream: TStream; aExtension: string)
                        : TAbstractResourceReader
class function FindReader(aStream: TStream) : TAbstractResourceReader
```

Visibility: public

Description: This method tries to find a resource reader able to read the stream passed as parameter.

If an extension is specified, only readers matching that extension are tried. The extension is case-insensitive and includes the leading dot, unless the empty string is passed (which means "no extension", e.g. a unix executable, which doesn't have an extension).

If a suitable reader is found, an instance of that reader is returned.

**Remark:** To make a resource reader class known, add that resource reader unit to the uses clause of your program.

Errors: If no suitable reader is found, an EResourceReaderNotFoundException (132) exception is raised.

See also: TAbstractResourceReader (143)

### 21.22.11 TResources.MoveFrom

Synopsis: Moves all resources of another TResources object to itself

Declaration: 

```
procedure MoveFrom(aResources: TResources)
```

Visibility: public

Description: This method takes all resources from object aResources and adds them to this object. aResources object is left empty.

Errors: If a resource with the same type, name and language ID already exists, an EResourceDuplicateException (132) exception is raised.

See also: TResources.Add (155)

### 21.22.12 TResources.Remove

Synopsis: Removes a resource

Declaration: 

```
function Remove(aType: TResourceDesc; aName: TResourceDesc;
               const aLangID: TLangID) : TAbstractResource; Overload
function Remove(aType: TResourceDesc; aName: TResourceDesc)
               : TAbstractResource; Overload
function Remove(aResource: TAbstractResource) : TAbstractResource
               ; Overload
function Remove(aIndex: Integer) : TAbstractResource; Overload
```

Visibility: public

Description: This method searches for a resource based on passed parameters and removes it from the object.  
The removed resource is then returned.

Errors: If no matching resource is found, an `EResourceNotFoundException` (132) exception is raised.

See also: `TResources.Find` (156)

### 21.22.13 TResources.LoadFromStream

Synopsis: Loads the contents of the object from a stream

Declaration: `procedure LoadFromStream(aStream: TStream); Overload`  
`procedure LoadFromStream(aStream: TStream;`  
`aReader: TAbstractResourceReader); Overload`

Visibility: public

Description: This method clears the `TResources` object and loads its contents from the stream passed as parameter.  
If a reader is specified, that reader is used. Otherwise, the stream is probed to find a suitable reader.

**Remark:** If `CacheData` (161) is set to `true`, the stream will be used as the underlying stream of each resource `RawData` (142) stream. This means that the stream must not be freed until all resources in the `TResources` object are freed: this happens when the `TResources` object is cleared or is loaded again from a different source. If you need to free the stream while there are still resources, disable the copy-on-write mechanism by setting `CacheData` (161) property to `false`.

Errors: If no reader is passed and probing fails, an `EResourceReaderNotFoundException` (132) exception is raised.

See also: `TAbstractResourceReader` (143), `TAbstractResource.RawData` (142), `TAbstractResource.CacheData` (142), `TResources.CacheData` (161), `TResources.LoadFromFile` (158), `TResources.Clear` (156), `TResources.FindReader` (157)

### 21.22.14 TResources.LoadFromFile

Synopsis: Loads the contents of the object from a file

Declaration: `procedure LoadFromFile(aFileName: string); Overload`  
`procedure LoadFromFile(aFileName: string;`  
`aReader: TAbstractResourceReader); Overload`

Visibility: public

Description: This method clears the `TResources` object and loads its contents from the file passed as parameter.  
If a reader is specified, that reader is used. Otherwise, the file is probed to find a suitable reader.

**Remark:** If `CacheData` (161) is set to `true`, the file will be left open and used as the underlying stream of each resource `RawData` (142) stream. This means that the file will be open until the `TResources` object is cleared or is loaded again from a different source. If you want the file to be closed while there are still resources, disable the copy-on-write mechanism by setting `CacheData` (161) property to `false`.

#### Sample code

This code extracts resources from an exe file

```

var
  resources : TResources;
begin
  resources:=TResources.Create;
  resources.LoadFromFile('myexe.exe');
  resources.WriteToFile('myexe.res');
  resources.Free;
end;

```

**Errors:** If no reader is passed and probing fails, an `EResourceReaderNotFoundException` (132) exception is raised.

See also: `TAbstractResourceReader` (143), `TAbstractResource.RawData` (142), `TAbstractResource.CacheData` (142), `TResources.CacheData` (161), `TResources.LoadFromStream` (158), `TResources.Clear` (156), `TResources.FindReader` (157)

### 21.22.15 TResources.RegisterReader

**Synopsis:** Registers a resource reader class

**Declaration:** `class procedure RegisterReader(const aExtension: string;  
aClass: TResourceReaderClass)`

**Visibility:** public

**Description:** This class method registers a resource reader class.

When registered, a class is known to `TResources` class, and can be used by `FindReader` (157), `LoadFromStream` (158) and `LoadFromFile` (158) methods when probing.

Usually this method is called in the `initialization` section of the unit implementing a `TAbstractResourceReader` (143) descendant.

A class can be registered multiple times, one for each extension it is able to read. Multiple class can be registered for the same extension (e.g. both a coff and a elf reader can be registered for the .o extension). The extension must include the leading dot unless the empty string is used (which means "no extension", e.g. a unix executable, which doesn't have an extension).

See also: `TAbstractResourceReader` (143), `TResources.FindReader` (157), `TResources.LoadFromStream` (158), `TResources.LoadFromFile` (158)

### 21.22.16 TResources.RegisterWriter

**Synopsis:** Registers a resource writer class

**Declaration:** `class procedure RegisterWriter(const aExtension: string;  
aClass: TResourceWriterClass)`

**Visibility:** public

**Description:** This class method registers a resource writer class.

When registered, a class is known to `TResources` class, and can be used by `WriteToFile` (160) method when probing.

Usually this method is called in the `initialization` section of the unit implementing a `TAbstractResourceWriter` (148) descendant.

A class can be registered multiple times, one for each extension it is able to write. Multiple class can be registered for the same extension (e.g. both a coff and a elf writer can be registered for the .o



extension) although only the first one found will be used when probing. The extension must include the leading dot unless the empty string is used (which means "no extension", e.g. a unix executable, which doesn't have an extension).

See also: [TAbstractResourceWriter \(148\)](#), [TResources.WriteToFile \(160\)](#)

### 21.22.17 TResources.WriteToStream

Synopsis: Writes the contents of the object to a stream

Declaration: `procedure WriteToStream(aStream: TStream;  
aWriter: TAbstractResourceWriter)`

Visibility: public

Description: This method writes the contents of the object to a stream via the specified [TAbstractResourceWriter \(148\)](#) descendant

See also: [TAbstractResourceWriter \(148\)](#), [TResources.WriteToFile \(160\)](#)

### 21.22.18 TResources.WriteToFile

Synopsis: Writes the contents of the object to a file

Declaration: `procedure WriteToFile(aFileName: string); Overload  
procedure WriteToFile(aFileName: string;  
aWriter: TAbstractResourceWriter); Overload`

Visibility: public

Description: This method writes the contents of the object to a file whose name is passed as parameter.

If a writer is specified, that writer is used. Otherwise, the first registered writer matching the file name extension is used.

Errors: If no writer is passed and no suitable writer is found, an [EResourceWriterNotFoundException \(133\)](#) exception is raised.

See also: [TAbstractResourceWriter \(148\)](#), [TResources.WriteToStream \(160\)](#)

### 21.22.19 TResources.Count

Synopsis: The number of resources in the object

Declaration: `Property Count : LongWord`

Visibility: public

Access: Read

See also: [TResources.Items \(161\)](#)

### 21.22.20 TResources.Items

Synopsis: Indexed array of resources in the object

Declaration: `Property Items[Index: Integer]: TAbstractResource; default`

Visibility: public

Access: Read

Description: This property can be used to access all resources in the object.

**Remark:** This array is 0-based: valid elements range from 0 to Count (160)-1.

See also: TResources.Count (160), TAbstractResource (133)

### 21.22.21 TResources.CacheData

Synopsis: Controls the copy-on-write behaviour of all resources

Declaration: `Property CacheData : Boolean`

Visibility: public

Access: Read,Write

Description: Changing this property changes CacheData (142) property of all resources contained in the object.

This property affects existing resources and resources that are added or loaded.

By default, CacheData is true.

See also: TAbstractResource.CacheData (142), TAbstractResource.RawData (142)

## Chapter 22

# Reference for unit 'resourcetree'

### 22.1 Used units

Table 22.1: Used units by unit 'resourcetree'

Name	Page
Classes	??
resource	<a href="#">127</a>
System	??
sysutils	??

### 22.2 Overview

This unit implements classes that represent an ordered tree of resources.

Such a tree is used internally by TResources ([162](#)) to speed up operations, and by certain resource readers and writers that deal with resource formats where data is stored as ordered trees of resources. For this reason, only implementors of resource readers and writers should be interested in these classes.

A tree begins with a root node, which is an instance of TRootResTreeNode ([169](#)). The root node contains type nodes, that contain name nodes, that contain language id nodes. Finally, a language id node contains a resource.

Each node contains its sub nodes in two lists: a Named list for nodes identified by a name (a string), and an ID list for nodes identified by an ID (an integer). In each list, nodes are sorted in ascending order.

Many resource formats (PECOFF, ELF, Mach-O, and external resource files) use this exact format to store resource information.

**Remark:** When a tree is destroyed, the resources it references aren't destroyed.

## 22.3 TResourceTreeNode

### 22.3.1 Description

This class represents a node in a resource tree.

**Remark:** An object of this class should never be directly instantiated. To create a node, call `CreateSubNode` (165) method of an already existing node.

### 22.3.2 Method overview

Page	Method	Description
164	Add	Adds a new resource to the tree
165	Clear	Destroys all sub nodes
164	Create	
165	CreateResource	Creates a new resource
165	CreateSubNode	Creates a subnode
164	Destroy	Destroys the object.
166	Find	Searches for a resource
166	FindFreeID	Find a free ID to be used as a resource name
164	GetData	
164	GetIDCount	
164	GetIDEntry	
163	GetNamedCount	
163	GetNamedEntry	
164	InternalFind	
166	IsLeaf	Reports whether the node is a leaf node.
165	Remove	Removes a resource from the tree

### 22.3.3 Property overview

Page	Properties	Access	Description
169	Data	r	The resource contained in this node
169	DataRVA	rw	To be used by readers and writers
167	Desc	r	The description of the node
167	IDCount	r	The number of ID sub nodes of the node
168	IDEntries	r	Indexed array of ID sub nodes of the node
167	NamedCount	r	The number of named sub nodes of the node
167	NamedEntries	r	Indexed array of named sub nodes of the node
168	NameRVA	rw	To be used by readers and writers
166	Parent	r	
168	SubDirRVA	rw	To be used by readers and writers

### 22.3.4 TResourceTreeNode.GetNamedCount

Declaration: `function GetNamedCount : LongWord`

Visibility: protected

### 22.3.5 TResourceTreeNode.GetNamedEntry

Declaration: `function GetNamedEntry(index: Integer) : TResourceTreeNode`

Visibility: protected

### 22.3.6 TResourceTreeNode.GetIDCount

Declaration: `function GetIDCount : LongWord`

Visibility: `protected`

### 22.3.7 TResourceTreeNode.GetIDEntry

Declaration: `function GetIDEntry(index: Integer) : TResourceTreeNode`

Visibility: `protected`

### 22.3.8 TResourceTreeNode.GetData

Declaration: `function GetData : TAbstractResource; Virtual`

Visibility: `protected`

### 22.3.9 TResourceTreeNode.InternalFind

Declaration: `function InternalFind(aList: TFPList; aDesc: TResourceDesc;  
out index: Integer) : Boolean; Overload  
function InternalFind(aList: TFPList; aLangID: TLangID;  
out index: Integer) : Boolean; Overload  
function InternalFind(aType: TResourceDesc; aName: TResourceDesc;  
const aLangID: TLangID; const noLangID: Boolean;  
const toDelete: Boolean) : TAbstractResource  
; Virtual; Abstract; Overload`

Visibility: `protected`

### 22.3.10 TResourceTreeNode.Create

Declaration: `constructor Create; Virtual; Overload`

Visibility: `protected`

### 22.3.11 TResourceTreeNode.Destroy

Synopsis: Destroys the object.

Declaration: `destructor Destroy; Override`

Visibility: `public`

**Description:** Only root nodes (instances of `TRootResTreeNode` (169)) should be destroyed. Children nodes are destroyed by their parent when needed.

### 22.3.12 TResourceTreeNode.Add

Synopsis: Adds a new resource to the tree

Declaration: `procedure Add(aResource: TAbstractResource); Virtual; Abstract`

Visibility: `public`

Description: This method adds a new resource to the tree, creating all needed sub nodes

**Remark:** This method should only be called on root nodes (instances of `TRootResTreeNode` (169)).

Errors: If a resource with the same type, name and language ID already exists, an `EResourceDuplicateException` (162) exception is raised.

See also: `TResourceTreeNode.Remove` (165)

### 22.3.13 TResourceTreeNode.CreateSubNode

Synopsis: Creates a subnode

Declaration: `function CreateSubNode(aDesc: TResourceDesc) : TResourceTreeNode  
; Virtual; Abstract`

Visibility: public

Description: This method creates a subnode, identified by the given resource description.

See also: `TResourceTreeNode.Desc` (167)

### 22.3.14 TResourceTreeNode.CreateResource

Synopsis: Creates a new resource

Declaration: `function CreateResource : TAbstractResource; Virtual`

Visibility: public

Description: This method creates a new resource.

A new resource is created and its type, name and language id are determined from the ancestor nodes in the tree hierarchy.

Usually `CreateResource` is called by resource readers that read files in which resources are stored as trees.

**Remark:** This method is meaningful only when called on leaf nodes (language id nodes).

See also: `TResourceTreeNode.IsLeaf` (166)

### 22.3.15 TResourceTreeNode.Clear

Synopsis: Destroys all sub nodes

Declaration: `procedure Clear`

Visibility: public

Description: This method destroys all sub nodes of the node.

### 22.3.16 TResourceTreeNode.Remove

Synopsis: Removes a resource from the tree

Declaration: `function Remove(aType: TResourceDesc; aName: TResourceDesc)  
: TAbstractResource; Overload  
function Remove(aType: TResourceDesc; aName: TResourceDesc;  
const aLangID: TLangID) : TAbstractResource; Overload`

Visibility: public

**Description:** This method searches for the specified resource and removes it from the tree. If a language ID is not provided, the first resource found that matches `aType` and `aName` is returned. The removed resource is then returned.

If no resource is found, `nil` is returned.

**Remark:** This method should only be called on root nodes (instances of `TRootResTreeNode` (169)).

See also: `TResourceTreeNode.Add` (164)

### 22.3.17 TResourceTreeNode.Find

Synopsis: Searches for a resource

**Declaration:** `function Find(aType: TResourceDesc; aName: TResourceDesc)  
: TAbstractResource; Overload  
function Find(aType: TResourceDesc; aName: TResourceDesc;  
const aLangID: TLangID) : TAbstractResource; Overload`

Visibility: public

**Description:** This method searches for a resource with the given type and name in the tree. If a language ID is not provided, the first resource found that matches `aType` and `aName` is returned.

If no resource is found, `nil` is returned.

**Remark:** This method should only be called on root nodes (instances of `TRootResTreeNode` (169)).

### 22.3.18 TResourceTreeNode.FindFreeID

Synopsis: Find a free ID to be used as a resource name

**Declaration:** `function FindFreeID(aType: TResourceDesc) : TResID; Virtual`

Visibility: public

**Description:** This method is used to find an available ID to be used as a name for a resource, given a resource type. It is used internally by `AddAutoID` (162) method of `TResources` (162).

**Remark:** This method should only be called on root nodes (instances of `TRootResTreeNode` (169)).

**Errors:** If there are no free ids left for the given resource type, an `ENoMoreFreeIDsException` (162) is raised.

### 22.3.19 TResourceTreeNode.IsLeaf

Synopsis: Reports whether the node is a leaf node.

**Declaration:** `function IsLeaf : Boolean; Virtual`

Visibility: public

**Description:** Returns `true` if the node is a leaf node. A leaf node is a language ID node.

### 22.3.20 TResourceTreeNode.Parent

**Declaration:** `Property Parent : TResourceTreeNode`

Visibility: protected

Access: Read

### 22.3.21 TResourceTreeNode.Desc

Synopsis: The description of the node

Declaration: `Property Desc : TResourceDesc`

Visibility: public

Access: Read

Description: The description of a node identifies that node. According to the type of the node, it can be a resource type, name or language id.

### 22.3.22 TResourceTreeNode.NamedCount

Synopsis: The number of named sub nodes of the node

Declaration: `Property NamedCount : LongWord`

Visibility: public

Access: Read

See also: `TResourceTreeNode.NamedEntries` ([167](#)), `TResourceTreeNode.IDCount` ([167](#))

### 22.3.23 TResourceTreeNode.NamedEntries

Synopsis: Indexed array of named sub nodes of the node

Declaration: `Property NamedEntries[index: Integer]: TResourceTreeNode`

Visibility: public

Access: Read

Description: This property can be used to access all named sub nodes in the node.

**Remark:** This array is 0-based: valid elements range from 0 to `NamedCount` ([167](#))-1.

See also: `TResourceTreeNode.NamedCount` ([167](#)), `TResourceTreeNode.IDEntries` ([168](#))

### 22.3.24 TResourceTreeNode.IDCount

Synopsis: The number of ID sub nodes of the node

Declaration: `Property IDCount : LongWord`

Visibility: public

Access: Read

See also: `TResourceTreeNode.IDEntries` ([168](#)), `TResourceTreeNode.NamedCount` ([167](#))



### 22.3.25 TResourceTreeNode.IDEntries

Synopsis: Indexed array of ID sub nodes of the node

Declaration: `Property IDEntries[index: Integer]: TResourceTreeNode`

Visibility: public

Access: Read

Description: This property can be used to access all ID sub nodes in the node.

**Remark:** This array is 0-based: valid elements range from 0 to IDCount (167)-1.

See also: TResourceTreeNode.IDCount (167), TResourceTreeNode.NamedEntries (167)

### 22.3.26 TResourceTreeNode.NameRVA

Synopsis: To be used by readers and writers

Declaration: `Property NameRVA : LongWord`

Visibility: public

Access: Read,Write

Description: This property can be freely used by resource readers and writers to store a file offset or address needed to load or write other data, since it isn't used by TResourceTreeNode (163) or TResources (162).

**Remark:** Do not rely on the value of this property when accessing a new tree: other readers or writers could have changed it for their internal operations.

See also: TResourceTreeNode.SubDirRVA (168), TResourceTreeNode.DataRVA (169)

### 22.3.27 TResourceTreeNode.SubDirRVA

Synopsis: To be used by readers and writers

Declaration: `Property SubDirRVA : LongWord`

Visibility: public

Access: Read,Write

Description: This property can be freely used by resource readers and writers to store a file offset or address needed to load or write other data, since it isn't used by TResourceTreeNode (163) or TResources (162).

**Remark:** Do not rely on the value of this property when accessing a new tree: other readers or writers could have changed it for their internal operations.

See also: TResourceTreeNode.NameRVA (168), TResourceTreeNode.DataRVA (169)

### 22.3.28 TResourceTreeNode.DataRVA

Synopsis: To be used by readers and writers

Declaration: `Property DataRVA : LongWord`

Visibility: public

Access: Read, Write

Description: This property can be freely used by resource readers and writers to store a file offset or address needed to load or write other data, since it isn't used by TResourceTreeNode (163) or TResources (162).

**Remark:** Do not rely on the value of this property when accessing a new tree: other readers or writers could have changed it for their internal operations.

See also: TResourceTreeNode.NameRVA (168), TResourceTreeNode.SubDirRVA (168)

### 22.3.29 TResourceTreeNode.Data

Synopsis: The resource contained in this node

Declaration: `Property Data : TAbstractResource`

Visibility: public

Access: Read

Description: This property references the resource contained in this node.

**Remark:** This property is meaningful only on leaf nodes (language id nodes).

See also: TResourceTreeNode.IsLeaf (166)

## 22.4 TRootResTreeNode

### 22.4.1 Description

This node represents the root node of a resource tree.

It is the only node which must be created with its constructor: other nodes in the tree are automatically created when adding a resource, or calling CreateSubNode (165) method of their parent.

Normally all search, add and delete operations on the tree are performed by calling methods of this node.

### 22.4.2 Method overview

Page	Method	Description
<a href="#">170</a>	Add	
<a href="#">170</a>	Create	Creates a new root node
<a href="#">170</a>	CreateSubNode	
<a href="#">170</a>	FindFreeID	
<a href="#">170</a>	InternalFind	

### 22.4.3 TRootResTreeNode.InternalFind

Declaration: `function InternalFind(aType: TResourceDesc; aName: TResourceDesc;  
const aLangID: TLangID; const noLangID: Boolean;  
const toDelete: Boolean) : TAbstractResource  
; Override`

Visibility: protected

### 22.4.4 TRootResTreeNode.Create

Synopsis: Creates a new root node

Declaration: `constructor Create; Override`

Visibility: public

Description: This method creates a new tree, represented by a root node without children.

Other nodes in the tree are automatically created when adding a resource, or calling `CreateSubNode` (165) method of their parent.

See also: `TResourceTreeNode.CreateSubNode` (165), `TResourceTreeNode.Add` (164)

### 22.4.5 TRootResTreeNode.CreateSubNode

Declaration: `function CreateSubNode(aDesc: TResourceDesc) : TResourceTreeNode  
; Override`

Visibility: public

### 22.4.6 TRootResTreeNode.Add

Declaration: `procedure Add(aResource: TAbstractResource); Override`

Visibility: public

### 22.4.7 TRootResTreeNode.FindFreeID

Declaration: `function FindFreeID(aType: TResourceDesc) : TResID; Override`

Visibility: public

## Chapter 23

# Reference for unit 'resreader'

### 23.1 Used units

Table 23.1: Used units by unit 'resreader'

Name	Page
Classes	??
resource	<a href="#">127</a>
System	??
sysutils	??

### 23.2 Overview

This unit contains `TResResourceReader` ([171](#)), a `TAbstractResourceReader` ([171](#)) descendant that is able to read .res resource files.

Adding this unit to a program's `uses` clause registers class `TResResourceReader` ([171](#)) with `TResources` ([171](#)).

### 23.3 TResResourceReader

#### 23.3.1 Description

This class provides a reader for .res resource files.

A .res file is a standard Windows file type that contains resources. This is not an object file format, so it's not suitable for being linked with other object files. For this reason, it is a good choice for a platform-independent format to store resources.

See also: `TAbstractResourceReader` ([171](#)), `TResResourceWriter` ([171](#))

**23.3.2 Method overview**

Page	Method	Description
<a href="#">172</a>	CheckMagic	
<a href="#">172</a>	Create	
<a href="#">172</a>	Destroy	
<a href="#">172</a>	GetDescription	
<a href="#">172</a>	GetExtensions	
<a href="#">172</a>	Load	

**23.3.3 TResResourceReader.GetExtensions**

Declaration: `function GetExtensions : string; Override`

Visibility: `protected`

**23.3.4 TResResourceReader.GetDescription**

Declaration: `function GetDescription : string; Override`

Visibility: `protected`

**23.3.5 TResResourceReader.Load**

Declaration: `procedure Load(aResources: TResources; aStream: TStream); Override`

Visibility: `protected`

**23.3.6 TResResourceReader.CheckMagic**

Declaration: `function CheckMagic(aStream: TStream) : Boolean; Override`

Visibility: `protected`

**23.3.7 TResResourceReader.Create**

Declaration: `constructor Create; Override`

Visibility: `public`

**23.3.8 TResResourceReader.Destroy**

Declaration: `destructor Destroy; Override`

Visibility: `public`

## Chapter 24

# Reference for unit 'reswriter'

### 24.1 Used units

Table 24.1: Used units by unit 'reswriter'

Name	Page
Classes	??
resource	<a href="#">127</a>
System	??
sysutils	??

### 24.2 Overview

This unit contains `TResResourceWriter` ([173](#)), a `TAbstractResourceWriter` ([173](#)) descendant that is able to write .res resource files.

Adding this unit to a program's `uses` clause registers class `TResResourceWriter` ([173](#)) with TResources ([173](#)).

### 24.3 TResResourceWriter

#### 24.3.1 Description

This class provides a writer for .res resource files.

A .res file is a standard Windows file type that contains resources. This is not an object file format, so it's not suitable for being linked with other object files. For this reason, it is a good choice for a platform-independent format to store resources.

See also: `TAbstractResourceWriter` ([173](#)), `TResResourceReader` ([173](#))

**24.3.2 Method overview**

Page	Method	Description
<a href="#">174</a>	Create	
<a href="#">174</a>	GetDescription	
<a href="#">174</a>	GetExtensions	
<a href="#">174</a>	Write	

**24.3.3 TResResourceWriter.GetExtensions**

Declaration: `function GetExtensions : string; Override`

Visibility: `protected`

**24.3.4 TResResourceWriter.GetDescription**

Declaration: `function GetDescription : string; Override`

Visibility: `protected`

**24.3.5 TResResourceWriter.Write**

Declaration: `procedure Write(aResources: TResources; aStream: TStream); Override`

Visibility: `protected`

**24.3.6 TResResourceWriter.Create**

Declaration: `constructor Create; Override`

Visibility: `public`

## Chapter 25

# Reference for unit 'stringtableresource'

### 25.1 Used units

Table 25.1: Used units by unit 'stringtableresource'

Name	Page
Classes	??
resource	<a href="#">127</a>
System	??
sysutils	??

### 25.2 Overview

This unit contains `TStringTableResource` ([176](#)), a `TAbstractResource` ([175](#)) descendant specialized in handling resource of type `RT_STRING` ([175](#)).

Adding this unit to a program's `uses` clause registers class `TStringTableResource` ([176](#)) for type `RT_STRING` ([175](#)) with `TResourceFactory` ([175](#)).

### 25.3 Constants, types and variables

#### 25.3.1 Resource strings

```
SIndexOutOfBounds = 'String ID out of bounds: %d'
```

```
SNameNotAllowed =  
  'Resource ID must be an ordinal in the range 1-4096'
```



## 25.4 TStringTableIndexOutOfBoundsException

### 25.4.1 Description

This exception is raised when the id specified to access a string of TStringTableResource.Strings (179) property is not in the range TStringTableResource.FirstID (178) - TStringTableResource.LastID (179).

See also: TStringTableResource (176), TStringTableResource.Strings (179), TStringTableResource.FirstID (178), TStringTableResource.LastID (179)

## 25.5 TStringTableNameNotAllowedException

### 25.5.1 Description

This exception is raised by constructor TStringTableResource.Create (178) if the name of the resource isn't of type dtID (175) and/or its name is not in the range 1-4096.

See also: TStringTableResource.Create (178)

## 25.6 TStringTableResourceException

### 25.6.1 Description

Base class for string table resource-related exceptions

## 25.7 TStringTableResource

### 25.7.1 Description

This class represents a resource of type RT\_STRING (175).

A string table is a resource containing strings, identified by an integer id in the range 0-65535. A string table contains exactly 16 strings, and its name is an ID in the range 1-4096, determined by the highest 12 bits of the strings ID it contains, plus one. That is, a string table with 1 as name holds strings with IDs from 0 to 15, string table 2 contains strings with IDs from 16 to 31 and so on. There is no difference between an empty string and a non-existent string.

For these reasons, it is not possible to set the name of a string table: it is autogenerated from the value of FirstID (178) property. Moreover, Count (179) property is always 16.

Strings (179) property is provided to access and modify individual strings.

**Remark:** This class doesn't allow its type to be changed to anything else than RT\_BITMAP (175). Its name can't be changed too. Attempts to do so result in a EResourceDescChangeNotAllowedException (175).

### 25.7.2 Method overview

Page	Method	Description
<a href="#">177</a>	ChangeDescTypeAllowed	
<a href="#">177</a>	ChangeDescValueAllowed	
<a href="#">178</a>	Create	Creates a new string table resource
<a href="#">178</a>	Destroy	
<a href="#">177</a>	GetName	
<a href="#">177</a>	GetType	
<a href="#">177</a>	NotifyResourcesLoaded	
<a href="#">178</a>	UpdateRawData	

### 25.7.3 Property overview

Page	Properties	Access	Description
<a href="#">179</a>	Count	r	The number of strings contained in the string table
<a href="#">178</a>	FirstID	rw	The ID of first the string contained in the string table
<a href="#">179</a>	LastID	r	The ID of the last string contained in the string table
<a href="#">179</a>	Strings	rw	Indexed array of strings in the string table

### 25.7.4 TStringTableResource.GetType

Declaration: `function GetType : TResourceDesc; Override`

Visibility: `protected`

### 25.7.5 TStringTableResource.GetName

Declaration: `function GetName : TResourceDesc; Override`

Visibility: `protected`

### 25.7.6 TStringTableResource.ChangeDescTypeAllowed

Declaration: `function ChangeDescTypeAllowed(aDesc: TResourceDesc) : Boolean  
; Override`

Visibility: `protected`

### 25.7.7 TStringTableResource.ChangeDescValueAllowed

Declaration: `function ChangeDescValueAllowed(aDesc: TResourceDesc) : Boolean  
; Override`

Visibility: `protected`

### 25.7.8 TStringTableResource.NotifyResourcesLoaded

Declaration: `procedure NotifyResourcesLoaded; Override`

Visibility: `protected`

### 25.7.9 TStringTableResource.Create

Synopsis: Creates a new string table resource

Declaration: `constructor Create; Override`  
`constructor Create(aType: TResourceDesc; aName: TResourceDesc)`  
`; Override`

Visibility: public

Description: Please note that `aType` parameter is not used, since this class always uses `RT_STRING` (175) as type.

**Remark:** `aName` must be a `TResourceDesc` (175) of type `dtID` (175) and its value must be in the range 1-4096, otherwise an `EStringTableNameNotAllowedException` (176) exception is raised.

**Errors:** If `aName` is not of type `dtID` (175) and/or its value isn't in the range 1-4096, an `EStringTableNameNotAllowedException` (176) exception is raised.

See also: `TStringTableResource.FirstID` (178)

### 25.7.10 TStringTableResource.Destroy

Declaration: `destructor Destroy; Override`

Visibility: public

### 25.7.11 TStringTableResource.UpdateRawData

Declaration: `procedure UpdateRawData; Override`

Visibility: public

### 25.7.12 TStringTableResource.FirstID

Synopsis: The ID of first the string contained in the string table

Declaration: `Property FirstID : Word`

Visibility: public

Access: Read,Write

Description: This property holds the value of the ID of the first string of the table. It is a multiple of 16.

The name of the resource is determined by this property, so changing `FirstID` also changes the resource name.

**Remark:** If an attempt of setting this property to an integer that isn't a multiple of 16 is made, the value is automatically corrected to the closest multiple of 16 less than the value specified (e.g. setting it to 36 sets it to 32).

See also: `TStringTableResource` (176), `TStringTableResource.LastID` (179), `TStringTableResource.Strings` (179)

### 25.7.13 TStringTableResource.LastID

Synopsis: The ID of the last string contained in the string table

Declaration: `Property LastID : Word`

Visibility: `public`

Access: `Read`

Description: The value of this property is always `FirstID (178)+15`.

See also: `TStringTableResource (176)`, `TStringTableResource.FirstID (178)`, `TStringTableResource.Strings (179)`

### 25.7.14 TStringTableResource.Count

Synopsis: The number of strings contained in the string table

Declaration: `Property Count : Integer`

Visibility: `public`

Access: `Read`

Description: Since a string table resource always contains exactly 16 strings, this property is always 16

See also: `TStringTableResource (176)`, `TStringTableResource.FirstID (178)`

### 25.7.15 TStringTableResource.Strings

Synopsis: Indexed array of strings in the string table

Declaration: `Property Strings[id: Word]: string; default`

Visibility: `public`

Access: `Read,Write`

Description: This property can be used to access all strings in the object.

**Remark:** Strings are accessed by their ID: valid elements range from `FirstID (178)` to `LastID (179)`. If the index specified isn't in this range, an `EStringTableIndexOutOfBoundsException (176)` exception is raised.

**Remark:** If you need to access `RawData (175)` after you modified strings, be sure to call `UpdateRawData (175)` first. This isn't needed however when resource is written to a stream, since `TResources (175)` takes care of it.

See also: `TStringTableResource (176)`, `TStringTableResource.FirstID (178)`, `TStringTableResource.LastID (179)`

## Chapter 26

# Reference for unit 'versionconsts'

### 26.1 Used units

Table 26.1: Used units by unit 'versionconsts'

Name	Page
System	??

### 26.2 Overview

This unit contains constants used by TVersionResource ([180](#)).

Constants for TVersionFixedInfo.FileFlags ([180](#)):

- VS\_FF\_DEBUG ([185](#)).
- VS\_FF\_INFOINFERRED ([185](#)).
- VS\_FF\_PATCHED ([185](#)).
- VS\_FF\_PRERELEASE ([185](#)).
- VS\_FF\_PRIVATEBUILD ([185](#)).
- VS\_FF\_SPECIALBUILD ([185](#)).

Constants for TVersionFixedInfo.FileOS ([180](#)):

- VOS\_UNKNOWN ([184](#))
- VOS\_DOS ([184](#))
- VOS\_OS216 ([184](#))
- VOS\_OS232 ([184](#))
- VOS\_NT ([184](#))
- VOS\_\_WINDOWS16 ([185](#))

- VOS\_\_WINDOWS32 (185)
- VOS\_\_PM16 (184)
- VOS\_\_PM32 (185)
- VOS\_DOS\_WINDOWS16 (184)
- VOS\_DOS\_WINDOWS32 (184)
- VOS\_OS216\_PM16 (184)
- VOS\_OS232\_PM32 (184)
- VOS\_NT\_WINDOWS32 (184)

Constants for TVersionFixedInfo.FileType (180):

- VFT\_UNKNOWN (183)
- VFT\_APP (183)
- VFT\_DLL (183)
- VFT\_DRV (183)
- VFT\_FONT (183)
- VFT\_VXD (184)
- VFT\_STATIC\_LIB (183)

Constants for TVersionFixedInfo.FileSubType (180):

- VFT2\_UNKNOWN (183)
- VFT2\_DRV\_COMM (182)
- VFT2\_DRV\_PRINTER (182)
- VFT2\_DRV\_KEYBOARD (182)
- VFT2\_DRV\_LANGUAGE (182)
- VFT2\_DRV\_DISPLAY (182)
- VFT2\_DRV\_MOUSE (182)
- VFT2\_DRV\_NETWORK (182)
- VFT2\_DRV\_SYSTEM (183)
- VFT2\_DRV\_INSTALLABLE (182)
- VFT2\_DRV\_SOUND (182)
- VFT2\_FONT\_RASTER (183)
- VFT2\_FONT\_VECTOR (183)
- VFT2\_FONT\_TRUETYPE (183)

## 26.3 Constants, types and variables

### 26.3.1 Constants

VFT2\_DRV\_COMM = \$0000000A

This constant is used for TVersionFixedInfo.FileSubType (180) when TVersionFixedInfo.FileType (180) is VFT\_DRV (183).

VFT2\_DRV\_DISPLAY = \$00000004

This constant is used for TVersionFixedInfo.FileSubType (180) when TVersionFixedInfo.FileType (180) is VFT\_DRV (183).

VFT2\_DRV\_INSTALLABLE = \$00000008

This constant is used for TVersionFixedInfo.FileSubType (180) when TVersionFixedInfo.FileType (180) is VFT\_DRV (183).

VFT2\_DRV\_KEYBOARD = \$00000002

This constant is used for TVersionFixedInfo.FileSubType (180) when TVersionFixedInfo.FileType (180) is VFT\_DRV (183).

VFT2\_DRV\_LANGUAGE = \$00000003

This constant is used for TVersionFixedInfo.FileSubType (180) when TVersionFixedInfo.FileType (180) is VFT\_DRV (183).

VFT2\_DRV\_MOUSE = \$00000005

This constant is used for TVersionFixedInfo.FileSubType (180) when TVersionFixedInfo.FileType (180) is VFT\_DRV (183).

VFT2\_DRV\_NETWORK = \$00000006

This constant is used for TVersionFixedInfo.FileSubType (180) when TVersionFixedInfo.FileType (180) is VFT\_DRV (183).

VFT2\_DRV\_PRINTER = \$00000001

This constant is used for TVersionFixedInfo.FileSubType (180) when TVersionFixedInfo.FileType (180) is VFT\_DRV (183).

VFT2\_DRV\_SOUND = \$00000009

This constant is used for TVersionFixedInfo.FileSubType (180) when TVersionFixedInfo.FileType (180) is VFT\_DRV (183).

VFT2\_DRV\_SYSTEM = \$00000007

This constant is used for TVersionFixedInfo.FileSubType (180) when TVersionFixedInfo.FileType (180) is VFT\_DRV (183).

VFT2\_FONT\_RASTER = \$00000001

This constant is used for TVersionFixedInfo.FileSubType (180) when TVersionFixedInfo.FileType (180) is VFT\_FONT (183).

VFT2\_FONT\_TRUETYPE = \$00000003

This constant is used for TVersionFixedInfo.FileSubType (180) when TVersionFixedInfo.FileType (180) is VFT\_FONT (183).

VFT2\_FONT\_VECTOR = \$00000002

This constant is used for TVersionFixedInfo.FileSubType (180) when TVersionFixedInfo.FileType (180) is VFT\_FONT (183).

VFT2\_UNKNOWN = \$00000000

This constant is used for TVersionFixedInfo.FileSubType (180).

VFT\_APP = \$00000001

This constant is used for TVersionFixedInfo.FileType (180).

VFT\_DLL = \$00000002

This constant is used for TVersionFixedInfo.FileType (180).

VFT\_DRV = \$00000003

This constant is used for TVersionFixedInfo.FileType (180).

The device driver type is specified in TVersionFixedInfo.FileSubType (180).

VFT\_FONT = \$00000004

This constant is used for TVersionFixedInfo.FileType (180).

The font driver type is specified in TVersionFixedInfo.FileSubType (180).

VFT\_STATIC\_LIB = \$00000007

This constant is used for TVersionFixedInfo.FileType (180).

VFT\_UNKNOWN = \$00000000

This constant is used for TVersionFixedInfo.FileType (180).

VFT\_VXD = \$00000005



This constant is used for TVersionFixedInfo.FileType ([180](#)).

VOS\_DOS = \$00010000

This constant is used for TVersionFixedInfo.FileOS ([180](#)).

VOS\_DOS\_WINDOWS16 = \$00010001

This constant is used for TVersionFixedInfo.FileOS ([180](#)).

VOS\_DOS\_WINDOWS32 = \$00010004

This constant is used for TVersionFixedInfo.FileOS ([180](#)).

VOS\_NT = \$00040000

This constant is used for TVersionFixedInfo.FileOS ([180](#)).

VOS\_NT\_WINDOWS32 = \$00040004

This constant is used for TVersionFixedInfo.FileOS ([180](#)).

VOS\_OS216 = \$00020000

This constant is used for TVersionFixedInfo.FileOS ([180](#)).

VOS\_OS216\_PM16 = \$00020002

This constant is used for TVersionFixedInfo.FileOS ([180](#)).

VOS\_OS232 = \$00030000

This constant is used for TVersionFixedInfo.FileOS ([180](#)).

VOS\_OS232\_PM32 = \$00030003

This constant is used for TVersionFixedInfo.FileOS ([180](#)).

VOS\_UNKNOWN = \$00000000

This constant is used for TVersionFixedInfo.FileOS ([180](#)).

VOS\_\_BASE = \$00000000

This constant is used for TVersionFixedInfo.FileOS ([180](#)).

VOS\_\_PM16 = \$00000002

This constant is used for TVersionFixedInfo.FileOS ([180](#)).

VOS\_\_PM32 = \$00000003

This constant is used for `TVersionFixedInfo.FileOS` (180).

`VOS__WINDOWS16 = $00000001`

This constant is used for `TVersionFixedInfo.FileOS` (180).

`VOS__WINDOWS32 = $00000004`

This constant is used for `TVersionFixedInfo.FileOS` (180).

`VS_FFI_FILEFLAGSMASK = $0000003F`

This constant is used mainly for `TVersionFixedInfo.FileFlagsMask` (180) to signal which bits are used in `TVersionFixedInfo.FileFlags` (180) field.

`VS_FF_DEBUG = $00000001`

This constant is used for `TVersionFixedInfo.FileFlags` (180).

`VS_FF_INFOINFERRED = $00000010`

This constant is used for `TVersionFixedInfo.FileFlags` (180).

`VS_FF_PATCHED = $00000004`

This constant is used for `TVersionFixedInfo.FileFlags` (180).

`VS_FF_PRERELEASE = $00000002`

This constant is used for `TVersionFixedInfo.FileFlags` (180).

`VS_FF_PRIVATEBUILD = $00000008`

This constant is used for `TVersionFixedInfo.FileFlags` (180).

When this flag is set, a `TVersionStringTable` (180) in `TVersionResource.StringFileInfo` (180) should contain an item with `PrivateBuild` as key.

`VS_FF_SPECIALBUILD = $00000020`

This constant is used for `TVersionFixedInfo.FileFlags` (180).

When this flag is set, a `TVersionStringTable` (180) in `TVersionResource.StringFileInfo` (180) should contain an item with `SpecialBuild` as key.

## Chapter 27

# Reference for unit 'versionresource'

### 27.1 Used units

Table 27.1: Used units by unit 'versionresource'

Name	Page
Classes	??
resource	<a href="#">127</a>
System	??
sysutils	??
versiontypes	<a href="#">191</a>

### 27.2 Overview

This unit contains TVersionResource ([187](#)), a TAbstractResource ([186](#)) descendant specialized in handling resource of type RT\_VERSION ([186](#)).

Adding this unit to a program's `uses` clause registers class TVersionResource ([187](#)) for type RT\_VERSION ([186](#)) with TResourceFactory ([186](#)).

### 27.3 Constants, types and variables

#### 27.3.1 Types

```
TVerBlockHeader = packed record
  length : Word;
  vallength : Word;
  ;
  valtype : Word;
  key : string;
end
```

This type is internally used by TVersionResource ([187](#))

## 27.4 TVersionResource

### 27.4.1 Description

This class represents a resource of type `RT_VERSION` (186).

A resource of this type provides version information for a Microsoft Windows executable or dll, which is shown when checking properties of a file in Windows Explorer.

Information is stored in `FixedInfo` (189), `StringFileInfo` (189) and `VarFileInfo` (190).

**Remark:** This class doesn't allow its type to be changed to anything else than `RT_VERSION` (186), and its name to be different from 1. Attempts to do so result in a `EResourceDescChangeNotAllowedException` (186).

**Remark:** If you need to access `RawData` (186) after you modified something, be sure to call `UpdateRawData` (186) first. This isn't needed however when resource is written to a stream, since `TResources` (186) takes care of it.

#### Sample code

This code creates a version information resource

```
const
  myVersion : TFileProductVersion = (1,2,0,0);

var
  resources : TResources;
  aRes : TVersionResource;
  st : TVersionStringTable;
  ti : TVerTranslationInfo;
begin
  aRes:=TVersionResource.Create(nil,nil); //it's always RT_VERSION and 1 respectively
  resources:=TResources.Create;
  resources.Add(aRes);

  aRes.FixedInfo.FileVersion:=myversion;
  aRes.FixedInfo.ProductVersion:=myversion;
  aRes.FixedInfo.FileFlagsMask:=VS_FFI_FILEFLAGSMASK;
  aRes.FixedInfo.FileFlags:=0;
  aRes.FixedInfo.FileOS:=VOS_NT_WINDOWS32;
  aRes.FixedInfo.FileType:=VFT_APP;
  aRes.FixedInfo.FileSubType:=0;
  aRes.FixedInfo.FileDate:=0;

  st:=TVersionStringTable.Create('041004B0'); //Italian, unicode codepage
  st.Add('CompanyName','Foo Corporation');
  st.Add('FileDescription','Foo suite core program');
  st.Add('FileVersion','1.2');
  st.Add('ProductVersion','1.2');
  aRes.StringFileInfo.Add(st);

  ti.language:=$0410; //Italian
  ti.codepage:=$04B0; //Unicode codepage
  aRes.VarFileInfo.Add(ti);

  resources.WriteToFile('myresource.res');
  resources.Free; //destroys aRes as well.
```

end;

See also: `TVersionResource.FixedInfo` ([189](#)), `TVersionResource.StringFileInfo` ([189](#)), `TVersionResource.VarFileInfo` ([190](#))

## 27.4.2 Method overview

Page	Method	Description
<a href="#">188</a>	<code>ChangeDescTypeAllowed</code>	
<a href="#">188</a>	<code>ChangeDescValueAllowed</code>	
<a href="#">189</a>	<code>Create</code>	Creates a new version information resource
<a href="#">189</a>	<code>Destroy</code>	
<a href="#">188</a>	<code>GetName</code>	
<a href="#">188</a>	<code>GetType</code>	
<a href="#">189</a>	<code>NotifyResourcesLoaded</code>	
<a href="#">189</a>	<code>UpdateRawData</code>	

## 27.4.3 Property overview

Page	Properties	Access	Description
<a href="#">189</a>	<code>FixedInfo</code>	r	Language independent part of version information
<a href="#">189</a>	<code>StringFileInfo</code>	r	Language dependent part of version information
<a href="#">190</a>	<code>VarFileInfo</code>	r	List of supported languages

## 27.4.4 TVersionResource.GetType

Declaration: `function GetType : TResourceDesc; Override`

Visibility: protected

## 27.4.5 TVersionResource.GetName

Declaration: `function GetName : TResourceDesc; Override`

Visibility: protected

## 27.4.6 TVersionResource.ChangeDescTypeAllowed

Declaration: `function ChangeDescTypeAllowed(aDesc: TResourceDesc) : Boolean; Override`

Visibility: protected

## 27.4.7 TVersionResource.ChangeDescValueAllowed

Declaration: `function ChangeDescValueAllowed(aDesc: TResourceDesc) : Boolean; Override`

Visibility: protected

### 27.4.8 TVersionResource.NotifyResourcesLoaded

Declaration: `procedure NotifyResourcesLoaded; Override`

Visibility: `protected`

### 27.4.9 TVersionResource.Create

Synopsis: Creates a new version information resource

Declaration: `constructor Create; Override`  
`constructor Create(aType: TResourceDesc; aName: TResourceDesc)`  
`; Override`

Visibility: `public`

Description: Please note that `aType` and `aName` parameters are not used, since this class always uses `RT_VERSION` (186) as type and 1 as name.

### 27.4.10 TVersionResource.Destroy

Declaration: `destructor Destroy; Override`

Visibility: `public`

### 27.4.11 TVersionResource.UpdateRawData

Declaration: `procedure UpdateRawData; Override`

Visibility: `public`

### 27.4.12 TVersionResource.FixedInfo

Synopsis: Language independent part of version information

Declaration: `Property FixedInfo : TVersionFixedInfo`

Visibility: `public`

Access: `Read`

See also: `TVersionFixedInfo` (186)

### 27.4.13 TVersionResource.StringFileInfo

Synopsis: Language dependent part of version information

Declaration: `Property StringFileInfo : TVersionStringFileInfo`

Visibility: `public`

Access: `Read`

See also: `TVersionStringFileInfo` (186)

#### 27.4.14 TVersionResource.VarFileInfo

Synopsis: List of supported languages

Declaration: `Property VarFileInfo : TVersionVarFileInfo`

Visibility: `public`

Access: `Read`

See also: `TVersionVarFileInfo` ([186](#))

## Chapter 28

# Reference for unit 'versiontypes'

### 28.1 Used units

Table 28.1: Used units by unit 'versiontypes'

Name	Page
Classes	??
resource	<a href="#">127</a>
System	??
sysutils	??

### 28.2 Overview

This unit contains classes used by TVersionResource ([191](#)).

### 28.3 Constants, types and variables

#### 28.3.1 Resource strings

```
SVerStrTableDuplicateKey = 'Duplicate key ''%s'''
```

```
SVerStrTableKeyNotFound = 'Key ''%s'' not found'
```

```
SVerStrTableNameNotAllowed =  
  'Name ''%s'' is not a valid 8-cipher hex sequence'
```

#### 28.3.2 Types

```
PVerTranslationInfo = ^TVerTranslationInfo
```

Pointer to a TVerTranslationInfo



```
TFileProductVersion = Array[0..3] of Word
```

This type is a 4-element array of words that is used to represent a file or product version.

Major version number is stored in the lowest word

### Example

Product version 4.2.1.1200 can be represented this way

```
const
  myver : TFileProductVersion = (4, 2, 1, 1200);

TVerTranslationInfo = packed record
  language : Word;
  codepage
    : Word;
end
```

This record represents a language id - codepage pair that is used by TVersionVarFileInfo (203).

## 28.4 EDuplicateKeyException

### 28.4.1 Description

This exception is raised when an attempt is made to add an item to a TVersionStringTable (199) object and the specified key is already present.

See also: TVersionStringTable.Add (200)

## 28.5 EKeyNotFoundException

### 28.5.1 Description

This exception is raised when the specified key is not found in the TVersionStringTable (199) object.

See also: TVersionStringTable.Delete (201), TVersionStringTable.Values (202)

## 28.6 ENameNotAllowedException

### 28.6.1 Description

This exception is raised when an attempt is made to set Name (201) property of TVersionStringTable (199) with a string that isn't an 8-cipher hexadecimal string.

See also: TVersionStringTable.Create (200), TVersionStringTable.Name (201)

## 28.7 EVersionStringTableException

### 28.7.1 Description

Base class for version string table - related exceptions

## 28.8 TVersionFixedInfo

### 28.8.1 Description

This class represents the language independent part of version information, and is always present in a version information resource.

See also: TVersionResource ([191](#)), TVersionResource.FixedInfo ([191](#))

### 28.8.2 Method overview

Page	Method	Description
<a href="#">193</a>	Create	

### 28.8.3 Property overview

Page	Properties	Access	Description
<a href="#">196</a>	FileDate	rw	The file creation timestamp.
<a href="#">194</a>	FileFlags	rw	The file flags
<a href="#">194</a>	FileFlagsMask	rw	Mask for FileFlags
<a href="#">194</a>	FileOS	rw	The operating system the file was designed to run on
<a href="#">195</a>	FileSubType	rw	Additional type information
<a href="#">195</a>	FileType	rw	The type of the file
<a href="#">193</a>	FileVersion	rw	The file version
<a href="#">193</a>	ProductVersion	rw	The product version

### 28.8.4 TVersionFixedInfo.Create

Declaration: `constructor Create`

Visibility: `public`

### 28.8.5 TVersionFixedInfo.FileVersion

Synopsis: The file version

Declaration: `Property FileVersion : TFileProductVersion`

Visibility: `public`

Access: Read,Write

See also: TFileProductVersion ([192](#))

### 28.8.6 TVersionFixedInfo.ProductVersion

Synopsis: The product version

Declaration: `Property ProductVersion : TFileProductVersion`

Visibility: `public`

Access: Read,Write

See also: TFileProductVersion ([192](#))

### 28.8.7 TVersionFixedInfo.FileFlagsMask

Synopsis: Mask for FileFlags

Declaration: `Property FileFlagsMask : LongWord`

Visibility: public

Access: Read,Write

Description: This property specifies which bits of FileFlags (194) are valid.

Usually it is VS\_FFI\_FILEFLAGSMASK (191).

See also: TVersionFixedInfo.FileFlags (194)

### 28.8.8 TVersionFixedInfo.FileFlags

Synopsis: The file flags

Declaration: `Property FileFlags : LongWord`

Visibility: public

Access: Read,Write

Description: It is a combination of the following values:

- VS\_FF\_DEBUG (191).
- VS\_FF\_INFOINFERRED (191).
- VS\_FF\_PATCHED (191).
- VS\_FF\_PRERELEASE (191).
- VS\_FF\_PRIVATEBUILD (191).
- VS\_FF\_SPECIALBUILD (191).

See also: TVersionFixedInfo.FileFlagsMask (194)

### 28.8.9 TVersionFixedInfo.FileOS

Synopsis: The operating system the file was designed to run on

Declaration: `Property FileOS : LongWord`

Visibility: public

Access: Read,Write

Description: It is one of the following values:

- VOS\_UNKNOWN (191)
- VOS\_DOS (191)
- VOS\_OS216 (191)
- VOS\_OS232 (191)
- VOS\_NT (191)

combined with one of the following values:

- VOS\_\_WINDOWS16 ([191](#))
- VOS\_\_WINDOWS32 ([191](#))
- VOS\_\_PM16 ([191](#))
- VOS\_\_PM32 ([191](#))

Note: some predefined combinations do exist:

- VOS\_DOS\_WINDOWS16 ([191](#))
- VOS\_DOS\_WINDOWS32 ([191](#))
- VOS\_OS216\_PM16 ([191](#))
- VOS\_OS232\_PM32 ([191](#))
- VOS\_NT\_WINDOWS32 ([191](#))

### 28.8.10 TVersionFixedInfo.FileType

Synopsis: The type of the file

Declaration: `Property FileType : LongWord`

Visibility: `public`

Access: `Read,Write`

Description: It can be one of the following values:

- VFT\_UNKNOWN ([191](#))
- VFT\_APP ([191](#))
- VFT\_DLL ([191](#))
- VFT\_DRV ([191](#))
- VFT\_FONT ([191](#))
- VFT\_VXD ([191](#))
- VFT\_STATIC\_LIB ([191](#))

See also: `TVersionFixedInfo.FileSubType` ([195](#))

### 28.8.11 TVersionFixedInfo.FileSubType

Synopsis: Additional type information

Declaration: `Property FileSubType : LongWord`

Visibility: `public`

Access: `Read,Write`

Description: This property is meaningful only for some values of `FileSubType` ([195](#)). For all other types, this property must be zero.

If `FileSubType` ([195](#)) is `VFT_DRV` ([191](#)):

- VFT2\_UNKNOWN ([191](#))
- VFT2\_DRV\_COMM ([191](#))

- VFT2\_DRV\_PRINTER ([191](#))
- VFT2\_DRV\_KEYBOARD ([191](#))
- VFT2\_DRV\_LANGUAGE ([191](#))
- VFT2\_DRV\_DISPLAY ([191](#))
- VFT2\_DRV\_MOUSE ([191](#))
- VFT2\_DRV\_NETWORK ([191](#))
- VFT2\_DRV\_SYSTEM ([191](#))
- VFT2\_DRV\_INSTALLABLE ([191](#))
- VFT2\_DRV\_SOUND ([191](#))

If FileSubType ([195](#)) is VFT\_FONT ([191](#)):

- VFT2\_UNKNOWN ([191](#))
- VFT2\_FONT\_RASTER ([191](#))
- VFT2\_FONT\_VECTOR ([191](#))
- VFT2\_FONT\_TRUETYPE ([191](#))

See also: TVersionFixedInfo.FileType ([195](#))

## 28.8.12 TVersionFixedInfo.FileDate

Synopsis: The file creation timestamp.

Declaration: Property FileDate : QWord

Visibility: public

Access: Read,Write

Description: It is a 64 bit timestamp.

## 28.9 TVersionStringFileInfo

### 28.9.1 Description

This class represents the language dependent part of version information.

It is a list of TVersionStringTable ([199](#)) objects, each representing information for a specific language-codepage combination.

See also: TVersionResource ([191](#)), TVersionResource.StringFileInfo ([191](#)), TVersionStringTable ([199](#))

### 28.9.2 Method overview

Page	Method	Description
<a href="#">197</a>	Add	Adds a new string table
<a href="#">198</a>	Clear	Deletes all string tables in the list
<a href="#">197</a>	Create	
<a href="#">198</a>	Delete	Deletes a string table
<a href="#">197</a>	Destroy	Destroys the object
<a href="#">197</a>	GetCount	
<a href="#">197</a>	GetItem	
<a href="#">197</a>	SetItem	

### 28.9.3 Property overview

Page	Properties	Access	Description
<a href="#">198</a>	Count	r	The number of string tables in the object
<a href="#">198</a>	Items	rw	Indexed array of string tables in the object

### 28.9.4 TVersionStringFileInfo.GetCount

Declaration: `function GetCount : Integer`

Visibility: `protected`

### 28.9.5 TVersionStringFileInfo.GetItem

Declaration: `function GetItem(index: Integer) : TVersionStringTable`

Visibility: `protected`

### 28.9.6 TVersionStringFileInfo.SetItem

Declaration: `procedure SetItem(index: Integer; aValue: TVersionStringTable)`

Visibility: `protected`

### 28.9.7 TVersionStringFileInfo.Create

Declaration: `constructor Create`

Visibility: `public`

### 28.9.8 TVersionStringFileInfo.Destroy

Synopsis: Destroys the object

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: All items are destroyed as well.

See also: `TVersionStringFileInfo.Clear` ([198](#))

### 28.9.9 TVersionStringFileInfo.Add

Synopsis: Adds a new string table

Declaration: `procedure Add(aStrTable: TVersionStringTable)`

Visibility: `public`

See also: `TVersionStringFileInfo.Delete` ([198](#))

### 28.9.10 TVersionStringFileInfo.Clear

Synopsis: Deletes all string tables in the list

Declaration: `procedure Clear`

Visibility: `public`

Description: This method empties the object. All string tables are freed.

See also: `TVersionStringFileInfo.Delete` ([198](#)), `TVersionStringFileInfo.Add` ([197](#))

### 28.9.11 TVersionStringFileInfo.Delete

Synopsis: Deletes a string table

Declaration: `procedure Delete(const aIndex: Integer)`

Visibility: `public`

Description: This method removes the string table identified by `aIndex` from the list. The string table is freed.

See also: `TVersionStringFileInfo.Clear` ([198](#)), `TVersionStringFileInfo.Add` ([197](#))

### 28.9.12 TVersionStringFileInfo.Count

Synopsis: The number of string tables in the object

Declaration: `Property Count : Integer`

Visibility: `public`

Access: `Read`

See also: `TVersionStringFileInfo.Items` ([198](#))

### 28.9.13 TVersionStringFileInfo.Items

Synopsis: Indexed array of string tables in the object

Declaration: `Property Items[index: Integer]: TVersionStringTable; default`

Visibility: `public`

Access: `Read, Write`

Description: This property can be used to access all string tables in the object.

**Remark:** This array is 0-based: valid elements range from 0 to `Count` ([198](#))-1.

See also: `TVersionStringFileInfo.Count` ([198](#)), `TVersionStringTable` ([199](#))

## 28.10 TVersionStringTable

### 28.10.1 Description

This class represents version information for a specific language-codepage combination.

It is contained in a TVersionStringFileInfo (196) object.

Information is stored as key-value pairs. The name of the string table specifies the language id - codepage to which the object applies.

There are some predefined keys that Microsoft Windows searches for. They are:

- Comments
- CompanyName
- FileDescription
- FileVersion
- InternalName
- LegalCopyright
- LegalTrademarks
- OriginalFilename
- PrivateBuild (only if VS\_FF\_PRIVATEBUILD (191) is set in TVersionFixedInfo.FileFlags (194))
- ProductName
- ProductVersion
- SpecialBuild (only if VS\_FF\_SPECIALBUILD (191) is set in TVersionFixedInfo.FileFlags (194))

See also: TVersionStringFileInfo (196), TVersionStringTable.Name (201), TVersionStringTable.Keys (202), TVersionStringTable.Values (202), TVersionStringTable.ValuesByIndex (202)

### 28.10.2 Method overview

Page	Method	Description
<a href="#">200</a>	Add	Adds a new item to the string table
<a href="#">201</a>	Clear	Deletes all items
<a href="#">200</a>	Create	Creates a new string table
<a href="#">201</a>	Delete	Deletes an item
<a href="#">200</a>	Destroy	Destroys the string table

### 28.10.3 Property overview

Page	Properties	Access	Description
<a href="#">201</a>	Count	r	The number of items in the object
<a href="#">202</a>	Keys	r	Indexed array of keys in the object
<a href="#">201</a>	Name	r	The name of the string table
<a href="#">202</a>	Values	rw	Array of values in the object, accessed by key
<a href="#">202</a>	ValuesByIndex	rw	Indexed array of values in the object



### 28.10.4 TVersionStringTable.Create

Synopsis: Creates a new string table

Declaration: `constructor Create(const aName: string)`

Visibility: `public`

Description: Creates a new string table with the name passed as `aName` parameter.

`aName` must be a hex representation of a 4-bytes unsigned number: first 4 ciphers represent the language id, and last 4 the codepage.

#### Sample code

This code creates a string table for Italian, with unicode codepage.

```
var
  st : TVersionStringTable;
begin
  //0410 = Italian
  //04B0 = unicode codepage
  st:=TVersionStringTable.Create('041004B0');

  //do something useful...

  st.Free;
end;
```

Errors: If name is not a valid 8-cipher hexadecimal string, an `ENameNotAllowedException` ([192](#)) exception is raised.

See also: `TVersionStringTable.Name` ([201](#))

### 28.10.5 TVersionStringTable.Destroy

Synopsis: Destroys the string table

Declaration: `destructor Destroy; Override`

Visibility: `public`

### 28.10.6 TVersionStringTable.Add

Synopsis: Adds a new item to the string table

Declaration: `procedure Add(const aKey: string; const aValue: string)`

Visibility: `public`

Description: This methods adds a new key-value pair to the string table.

Note that some predefined keys do exist. See `TVersionStringTable` ([199](#)) for further information.

Errors: If an item with the same key already exists, an `EDuplicateKeyException` ([192](#)) exception is raised.

See also: `TVersionStringTable` ([199](#)), `TVersionStringTable.Keys` ([202](#)), `TVersionStringTable.Values` ([202](#)), `TVersionStringTable.ValuesByIndex` ([202](#))

### 28.10.7 TVersionStringTable.Clear

Synopsis: Deletes all items

Declaration: `procedure Clear`

Visibility: `public`

Description: This method empties the object deleting all items.

See also: `TVersionStringTable.Delete` ([201](#))

### 28.10.8 TVersionStringTable.Delete

Synopsis: Deletes an item

Declaration: `procedure Delete(const aIndex: Integer); Overload`  
`procedure Delete(const aKey: string); Overload`

Visibility: `public`

Description: The item to delete can be specified by its index or by its key.

Errors: If `aKey` is not found, an `EKeyNotFoundException` ([192](#)) exception is raised.

See also: `TVersionStringTable.Keys` ([202](#)), `TVersionStringTable.Values` ([202](#)), `TVersionStringTable.ValuesByIndex` ([202](#))

### 28.10.9 TVersionStringTable.Name

Synopsis: The name of the string table

Declaration: `Property Name : string`

Visibility: `public`

Access: `Read`

Description: Name must be a hex representation of a 4-bytes unsigned number: first 4 ciphers represent the language id, and last 4 the codepage.

Errors: If an attempt is made to set `Name` with a string that isn't an 8-cipher hexadecimal string, an `ENameNotAllowedException` ([192](#)) exception is raised.

See also: `TVersionStringTable.Create` ([200](#))

### 28.10.10 TVersionStringTable.Count

Synopsis: The number of items in the object

Declaration: `Property Count : Integer`

Visibility: `public`

Access: `Read`

See also: `TVersionStringTable.ValuesByIndex` ([202](#))

### 28.10.11 TVersionStringTable.Keys

Synopsis: Indexed array of keys in the object

Declaration: `Property Keys[index: Integer]: string`

Visibility: public

Access: Read

Description: This property can be used to access all keys in the object.

Values associated to keys are stored in `ValuesByIndex` (202) property: a key and its value have the same index in the two properties.

**Remark:** This array is 0-based: valid elements range from 0 to `Count` (201)-1.

Note that some predefined keys do exist. See `TVersionStringTable` (199) for further information.

See also: `TVersionStringTable` (199), `TVersionStringTable.Values` (202), `TVersionStringTable.ValuesByIndex` (202)

### 28.10.12 TVersionStringTable.ValuesByIndex

Synopsis: Indexed array of values in the object

Declaration: `Property ValuesByIndex[index: Integer]: string`

Visibility: public

Access: Read,Write

Description: This property can be used to access all values in the object.

Keys associated to values are stored in `Keys` (202) property: a key and its value have the same index in the two properties.

**Remark:** This array is 0-based: valid elements range from 0 to `Count` (201)-1.

See also: `TVersionStringTable.Keys` (202), `TVersionStringTable.Values` (202)

### 28.10.13 TVersionStringTable.Values

Synopsis: Array of values in the object, accessed by key

Declaration: `Property Values[Key: string]: string; default`

Visibility: public

Access: Read,Write

Description: This property can be used to retrieve the value of an item when the corresponding key is known.

If you need to iterate over all values of the string table, use `ValuesByIndex` (202) instead.

If the key is not found, an `EKeyNotFoundException` (192) exception is raised.

See also: `TVersionStringTable.Keys` (202), `TVersionStringTable.ValuesByIndex` (202)

## 28.11 TVersionVarFileInfo

### 28.11.1 Description

This class represents the language-codepage pairs that the program or dll supports. It can be used to avoid including several RT\_VERSION (191) resources for each language-codepage supported.

It is a list of TVerTranslationInfo (192) records.

See also: TVersionResource.VarFileInfo (191), TVerTranslationInfo (192)

### 28.11.2 Method overview

Page	Method	Description
<a href="#">204</a>	Add	Adds a new translation information item
<a href="#">204</a>	Clear	Deletes all items
<a href="#">203</a>	Create	
<a href="#">204</a>	Delete	Deletes an item
<a href="#">204</a>	Destroy	Destroys the object
<a href="#">203</a>	GetCount	
<a href="#">203</a>	GetItem	
<a href="#">203</a>	SetItem	

### 28.11.3 Property overview

Page	Properties	Access	Description
<a href="#">204</a>	Count	r	The number of items in the object
<a href="#">205</a>	Items	rw	Indexed array of items in the object

### 28.11.4 TVersionVarFileInfo.GetCount

Declaration: `function GetCount : Integer`

Visibility: `protected`

### 28.11.5 TVersionVarFileInfo.GetItem

Declaration: `function GetItem(index: Integer) : TVerTranslationInfo`

Visibility: `protected`

### 28.11.6 TVersionVarFileInfo.SetItem

Declaration: `procedure SetItem(index: Integer; aValue: TVerTranslationInfo)`

Visibility: `protected`

### 28.11.7 TVersionVarFileInfo.Create

Declaration: `constructor Create`

Visibility: `public`

### 28.11.8 TVersionVarFileInfo.Destroy

Synopsis: Destroys the object

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: All items are destroyed as well.

See also: `TVersionVarFileInfo.Clear` ([204](#))

### 28.11.9 TVersionVarFileInfo.Add

Synopsis: Adds a new translation information item

Declaration: `procedure Add(aInfo: TVerTranslationInfo)`

Visibility: `public`

See also: `TVersionVarFileInfo.Items` ([205](#))

### 28.11.10 TVersionVarFileInfo.Clear

Synopsis: Deletes all items

Declaration: `procedure Clear`

Visibility: `public`

Description: This method empties the object deleting all items.

See also: `TVersionVarFileInfo.Delete` ([204](#))

### 28.11.11 TVersionVarFileInfo.Delete

Synopsis: Deletes an item

Declaration: `procedure Delete(const aIndex: Integer)`

Visibility: `public`

See also: `TVersionVarFileInfo.Items` ([205](#))

### 28.11.12 TVersionVarFileInfo.Count

Synopsis: The number of items in the object

Declaration: `Property Count : Integer`

Visibility: `public`

Access: `Read`

See also: `TVersionVarFileInfo.Items` ([205](#))

### 28.11.13 TVersionVarFileInfo.Items

Synopsis: Indexed array of items in the object

Declaration: `Property Items[index: Integer]: TVerTranslationInfo; default`

Visibility: `public`

Access: `Read, Write`

Description: This property can be used to access all translation information items in the object.

**Remark:** This array is 0-based: valid elements range from 0 to [Count \(204\)](#)-1.

See also: [TVersionVarFileInfo.Count \(204\)](#)

## Chapter 29

# Reference for unit 'winpeimagereader'

### 29.1 Used units

Table 29.1: Used units by unit 'winpeimagereader'

Name	Page
Classes	??
coffreader	<a href="#">51</a>
resource	<a href="#">127</a>
System	??
sysutils	??

### 29.2 Overview

This unit contains `TWinPEImageResourceReader` ([206](#)), a `TAbstractResourceReader` ([206](#)) descendant that is able to read Microsoft Windows PE image files (executables, dynamic link libraries and so on).

Adding this unit to a program's `uses` clause registers class `TWinPEImageResourceReader` ([206](#)) with `TResources` ([206](#)).

### 29.3 TWinPEImageResourceReader

#### 29.3.1 Description

This class provides a reader for Microsoft Windows PE image files containing resources.

PE is the file format used by Microsoft Windows executables, dynamic link libraries and so on.

**Remark:** This reader can only read full PE images, not COFF object files. Use `TCoffResourceReader` ([206](#)) instead.

See also: `TAbstractResourceReader` ([206](#)), `TCoffResourceReader` ([206](#))

### 29.3.2 Method overview

Page	Method	Description
<a href="#">207</a>	CheckDosStub	
<a href="#">207</a>	CheckMagic	
<a href="#">207</a>	CheckPESignature	
<a href="#">207</a>	Create	
<a href="#">208</a>	Destroy	
<a href="#">207</a>	GetDescription	
<a href="#">207</a>	GetExtensions	
<a href="#">207</a>	Load	

### 29.3.3 TWinPEImageResourceReader.CheckDosStub

Declaration: `function CheckDosStub(aStream: TStream) : Boolean`

Visibility: protected

### 29.3.4 TWinPEImageResourceReader.CheckPESignature

Declaration: `function CheckPESignature(aStream: TStream) : Boolean`

Visibility: protected

### 29.3.5 TWinPEImageResourceReader.GetExtensions

Declaration: `function GetExtensions : string; Override`

Visibility: protected

### 29.3.6 TWinPEImageResourceReader.GetDescription

Declaration: `function GetDescription : string; Override`

Visibility: protected

### 29.3.7 TWinPEImageResourceReader.Load

Declaration: `procedure Load(aResources: TResources; aStream: TStream); Override`

Visibility: protected

### 29.3.8 TWinPEImageResourceReader.CheckMagic

Declaration: `function CheckMagic(aStream: TStream) : Boolean; Override`

Visibility: protected

### 29.3.9 TWinPEImageResourceReader.Create

Declaration: `constructor Create; Override`

Visibility: public



### 29.3.10 TWinPEImageResourceReader.Destroy

Declaration: `destructor Destroy;`    `Override`

Visibility: `public`